



OpenShift Dedicated 4

Storage

Configuring storage for OpenShift Dedicated clusters

OpenShift Dedicated 4 Storage

Configuring storage for OpenShift Dedicated clusters

Legal Notice

Copyright © 2025 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

<http://creativecommons.org/licenses/by-sa/3.0/>

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, the Red Hat logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux[®] is the registered trademark of Linus Torvalds in the United States and other countries.

Java[®] is a registered trademark of Oracle and/or its affiliates.

XFS[®] is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL[®] is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js[®] is an official trademark of Joyent. Red Hat is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack[®] Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

Abstract

This document provides information about setting up storage for OpenShift Dedicated clusters.

Table of Contents

CHAPTER 1. OPENSIFT DEDICATED STORAGE OVERVIEW	5
1.1. GLOSSARY OF COMMON TERMS FOR OPENSIFT DEDICATED STORAGE	5
1.2. STORAGE TYPES	7
1.2.1. Ephemeral storage	7
1.2.2. Persistent storage	7
1.3. CONTAINER STORAGE INTERFACE (CSI)	7
1.4. DYNAMIC PROVISIONING	8
CHAPTER 2. UNDERSTANDING EPHEMERAL STORAGE	9
2.1. OVERVIEW	9
2.2. TYPES OF EPHEMERAL STORAGE	9
2.2.1. Root	9
2.2.2. Runtime	9
2.3. EPHEMERAL STORAGE MANAGEMENT	9
2.3.1. Ephemeral storage limits and requests units	10
2.3.2. Ephemeral storage requests and limits example	10
2.3.3. Ephemeral storage configuration effects pod scheduling and eviction	11
2.4. MONITORING EPHEMERAL STORAGE	11
CHAPTER 3. UNDERSTANDING PERSISTENT STORAGE	13
3.1. PERSISTENT STORAGE OVERVIEW	13
3.2. LIFECYCLE OF A VOLUME AND CLAIM	13
3.2.1. Provision storage	13
3.2.2. Bind claims	13
3.2.3. Use pods and claimed PVs	14
3.2.4. Release a persistent volume	14
3.2.5. Reclaim policy for persistent volumes	14
3.2.6. Reclaiming a persistent volume manually	15
3.2.7. Changing the reclaim policy of a persistent volume	15
3.3. PERSISTENT VOLUMES	16
3.3.1. Types of PVs	16
3.3.2. Capacity	17
3.3.3. Access modes	17
3.3.4. Phase	18
3.3.4.1. Last phase transition time	19
3.3.4.2. Mount options	19
3.4. PERSISTENT VOLUME CLAIMS	20
3.4.1. Storage classes	20
3.4.2. Access modes	21
3.4.3. Resources	21
3.4.4. Claims as volumes	21
3.4.5. Viewing PVC usage statistics	21
3.4.5.1. User permissions required to view PVC usage statistics	22
3.4.5.2. Viewing PVC usage statistics	22
3.5. BLOCK VOLUME SUPPORT	23
3.5.1. Block volume examples	24
3.6. USING FSGROUP TO REDUCE POD TIMEOUTS	26
CHAPTER 4. CONFIGURING PERSISTENT STORAGE	28
4.1. PERSISTENT STORAGE USING AWS ELASTIC BLOCK STORE	28
4.1.1. Creating the EBS storage class	28
4.1.2. Creating the persistent volume claim	28

4.1.3. Volume format	29
4.1.4. Maximum number of EBS volumes on a node	29
4.1.5. Encrypting container persistent volumes on AWS with a KMS key	29
4.1.6. Additional resources	31
4.2. PERSISTENT STORAGE USING GCE PERSISTENT DISK	31
4.2.1. Creating the GCE storage class	31
4.2.2. Creating the persistent volume claim	31
4.2.3. Volume format	32
CHAPTER 5. USING CONTAINER STORAGE INTERFACE (CSI)	33
5.1. CONFIGURING CSI VOLUMES	33
5.1.1. CSI architecture	33
5.1.1.1. External CSI controllers	33
5.1.1.2. CSI driver daemon set	34
5.1.2. CSI drivers supported by OpenShift Dedicated	34
5.1.3. Dynamic provisioning	35
5.1.4. Example using the CSI driver	36
5.2. MANAGING THE DEFAULT STORAGE CLASS	37
5.2.1. Overview	37
5.2.2. Managing the default storage class using the web console	37
5.2.3. Managing the default storage class using the CLI	38
5.2.4. Absent or multiple default storage classes	38
5.2.4.1. Multiple default storage classes	38
5.2.4.2. Absent default storage class	39
5.2.5. Changing the default storage class	39
5.3. AWS ELASTIC BLOCK STORE CSI DRIVER OPERATOR	40
5.3.1. Overview	40
5.3.2. About CSI	40
5.4. AWS ELASTIC FILE SERVICE CSI DRIVER OPERATOR	41
5.4.1. Overview	41
5.4.2. About CSI	41
5.4.3. Setting up the AWS EFS CSI Driver Operator	42
5.4.3.1. Obtaining a role Amazon Resource Name for Security Token Service	42
5.4.3.2. Installing the AWS EFS CSI Driver Operator	44
5.4.3.3. Installing the AWS EFS CSI Driver	45
5.4.4. Creating the AWS EFS storage class	46
5.4.4.1. Creating the AWS EFS storage class using the console	46
5.4.4.2. Creating the AWS EFS storage class using the CLI	46
5.4.5. AWS EFS CSI cross account support	47
5.4.6. Dynamic provisioning for Amazon Elastic File Storage	55
5.4.7. Creating static PVs with Amazon Elastic File Storage	56
5.4.8. Amazon Elastic File Storage security	57
5.4.9. AWS EFS storage CSI usage metrics	57
5.4.9.1. Usage metrics overview	57
5.4.9.2. Enabling usage metrics using the web console	58
5.4.9.3. Enabling usage metrics using the CLI	59
5.4.10. Amazon Elastic File Storage troubleshooting	59
5.4.11. Uninstalling the AWS EFS CSI Driver Operator	60
5.4.12. Additional resources	61
5.5. GCP PD CSI DRIVER OPERATOR	61
5.5.1. Overview	61
5.5.2. C3 instance type for bare metal and N4 machine series	62
5.5.2.1. C3 and N4 instance type limitations	62

5.5.2.2. Storage pools for hyperdisk-balanced disks overview	62
5.5.2.3. Setting up hyperdisk-balanced disks	62
5.5.3. About CSI	66
5.5.4. GCP PD CSI driver storage class parameters	66
5.5.5. Creating a custom-encrypted persistent volume	66
5.5.6. Additional resources	69
5.6. GOOGLE COMPUTE PLATFORM FILESTORE CSI DRIVER OPERATOR	69
5.6.1. Overview	69
5.6.2. About CSI	69
5.6.3. Installing the Google Cloud Filestore CSI Driver Operator	69
5.6.3.1. Preparing to install the Google Cloud Filestore CSI Driver Operator with Workload Identity	69
5.6.3.2. Installing the Google Cloud Filestore CSI Driver Operator	72
5.6.4. Creating a storage class for GCP Filestore Storage	73
5.6.5. NFS export options	74
5.6.6. Destroying clusters and GCP Filestore	76
5.6.7. Additional resources	76
CHAPTER 6. GENERIC EPHEMERAL VOLUMES	77
6.1. OVERVIEW	77
6.2. LIFECYCLE AND PERSISTENT VOLUME CLAIMS	77
6.3. SECURITY	78
6.4. PERSISTENT VOLUME CLAIM NAMING	78
6.5. CREATING GENERIC EPHEMERAL VOLUMES	78
CHAPTER 7. EXPANDING PERSISTENT VOLUMES	80
7.1. ENABLING VOLUME EXPANSION SUPPORT	80
7.2. EXPANDING CSI VOLUMES	80
7.3. EXPANDING LOCAL VOLUMES	81
7.4. EXPANDING PERSISTENT VOLUME CLAIMS (PVCS) WITH A FILE SYSTEM	81
7.5. RECOVERING FROM FAILURE WHEN EXPANDING VOLUMES	82
7.6. ADDITIONAL RESOURCES	82
CHAPTER 8. DYNAMIC PROVISIONING	83
8.1. ABOUT DYNAMIC PROVISIONING	83
8.2. AVAILABLE DYNAMIC PROVISIONING PLUGINS	83
8.3. DEFINING A STORAGE CLASS	84
8.3.1. Basic StorageClass object definition	84
8.3.2. Storage class annotations	85
8.3.3. AWS Elastic Block Store (EBS) object definition	85
8.3.4. GCE PersistentDisk (gcePD) object definition	86
8.4. CHANGING THE DEFAULT STORAGE CLASS	86

CHAPTER 1. OPENSIFT DEDICATED STORAGE OVERVIEW

OpenShift Dedicated supports multiple types of storage, both for on-premise and cloud providers. You can manage container storage for persistent and non-persistent data in an OpenShift Dedicated cluster.

1.1. GLOSSARY OF COMMON TERMS FOR OPENSIFT DEDICATED STORAGE

This glossary defines common terms that are used in the storage content.

Access modes

Volume access modes describe volume capabilities. You can use access modes to match persistent volume claim (PVC) and persistent volume (PV). The following are the examples of access modes:

- `ReadWriteOnce` (RWO)
- `ReadOnlyMany` (ROX)
- `ReadWriteMany` (RWX)
- `ReadWriteOncePod` (RWOP)

Config map

A config map provides a way to inject configuration data into pods. You can reference the data stored in a config map in a volume of type **ConfigMap**. Applications running in a pod can use this data.

Container Storage Interface (CSI)

An API specification for the management of container storage across different container orchestration (CO) systems.

Dynamic Provisioning

The framework allows you to create storage volumes on-demand, eliminating the need for cluster administrators to pre-provision persistent storage.

Ephemeral storage

Pods and containers can require temporary or transient local storage for their operation. The lifetime of this ephemeral storage does not extend beyond the life of the individual pod, and this ephemeral storage cannot be shared across pods.

fsGroup

The fsGroup defines a file system group ID of a pod.

hostPath

A hostPath volume in an OpenShift Container Platform cluster mounts a file or directory from the host node's filesystem into your pod.

KMS key

The Key Management Service (KMS) helps you achieve the required level of encryption of your data across different services. you can use the KMS key to encrypt, decrypt, and re-encrypt data.

Local volumes

A local volume represents a mounted local storage device such as a disk, partition or directory.

Nested mount points

A nested mount point is a mount point that attempts to use a mount point created by a previous volume.

Example pod definition with nested mount points

```
kind: Pod
apiVersion: v1
metadata:
  name: webapp
  labels:
    name: webapp
spec:
  containers:
    - name: webapp
      image: nginx
      ports:
        - containerPort: 80
          name: "http-server"
      volumeMounts:
        - mountPath: /mnt/web
          name: web
        - mountPath: /mnt/web/redis 1
          name: redis
  volumes:
    - name: redis
      persistentVolumeClaim:
        claimName: "redis"
    - name: web
      persistentVolumeClaim:
        claimName: "web"
```

1 Nested mount point

Do *not* use nested mount points because OpenShift Dedicated does not guarantee the order in which mount points are created. Such usage is prone to race conditions and undefined behavior.

OpenShift Data Foundation

A provider of agnostic persistent storage for OpenShift Container Platform supporting file, block, and object storage, either in-house or in hybrid clouds

Persistent storage

Pods and containers can require permanent storage for their operation. OpenShift Dedicated uses the Kubernetes persistent volume (PV) framework to allow cluster administrators to provision persistent storage for a cluster. Developers can use PVC to request PV resources without having specific knowledge of the underlying storage infrastructure.

Persistent volumes (PV)

OpenShift Dedicated uses the Kubernetes persistent volume (PV) framework to allow cluster administrators to provision persistent storage for a cluster. Developers can use PVC to request PV resources without having specific knowledge of the underlying storage infrastructure.

Persistent volume claims (PVCs)

You can use a PVC to mount a PersistentVolume into a Pod. You can access the storage without knowing the details of the cloud environment.

Pod

One or more containers with shared resources, such as volume and IP addresses, running in your OpenShift Dedicated cluster. A pod is the smallest compute unit defined, deployed, and managed.

Reclaim policy

A policy that tells the cluster what to do with the volume after it is released. A volume's reclaim policy can be **Retain**, **Recycle**, or **Delete**.

Role-based access control (RBAC)

Role-based access control (RBAC) is a method of regulating access to computer or network resources based on the roles of individual users within your organization.

Stateless applications

A stateless application is an application program that does not save client data generated in one session for use in the next session with that client.

Stateful applications

A stateful application is an application program that saves data to persistent disk storage. A server, client, and applications can use a persistent disk storage. You can use the **Statefulset** object in OpenShift Dedicated to manage the deployment and scaling of a set of Pods, and provides guarantee about the ordering and uniqueness of these Pods.

Static provisioning

A cluster administrator creates a number of PVs. PVs contain the details of storage. PVs exist in the Kubernetes API and are available for consumption.

Storage

OpenShift Dedicated supports many types of storage, both for on-premise and cloud providers. You can manage container storage for persistent and non-persistent data in an OpenShift Dedicated cluster.

Storage class

A storage class provides a way for administrators to describe the classes of storage they offer. Different classes might map to quality of service levels, backup policies, arbitrary policies determined by the cluster administrators.

1.2. STORAGE TYPES

OpenShift Dedicated storage is broadly classified into two categories, namely ephemeral storage and persistent storage.

1.2.1. Ephemeral storage

Pods and containers are ephemeral or transient in nature and designed for stateless applications. Ephemeral storage allows administrators and developers to better manage the local storage for some of their operations. For more information about ephemeral storage overview, types, and management, see [Understanding ephemeral storage](#).

1.2.2. Persistent storage

Stateful applications deployed in containers require persistent storage. OpenShift Dedicated uses a pre-provisioned storage framework called persistent volumes (PV) to allow cluster administrators to provision persistent storage. The data inside these volumes can exist beyond the lifecycle of an individual pod. Developers can use persistent volume claims (PVCs) to request storage requirements. For more information about persistent storage overview, configuration, and lifecycle, see [Understanding persistent storage](#).

1.3. CONTAINER STORAGE INTERFACE (CSI)

CSI is an API specification for the management of container storage across different container orchestration (CO) systems. You can manage the storage volumes within the container native environments, without having specific knowledge of the underlying storage infrastructure. With the CSI, storage works uniformly across different container orchestration systems, regardless of the storage vendors you are using. For more information about CSI, see [Using Container Storage Interface \(CSI\)](#) .

1.4. DYNAMIC PROVISIONING

Dynamic Provisioning allows you to create storage volumes on-demand, eliminating the need for cluster administrators to pre-provision storage. For more information about dynamic provisioning, see [Dynamic provisioning](#).

CHAPTER 2. UNDERSTANDING EPHEMERAL STORAGE

2.1. OVERVIEW

In addition to persistent storage, pods and containers can require ephemeral or transient local storage for their operation. The lifetime of this ephemeral storage does not extend beyond the life of the individual pod, and this ephemeral storage cannot be shared across pods.

Pods use ephemeral local storage for scratch space, caching, and logs. Issues related to the lack of local storage accounting and isolation include the following:

- Pods cannot detect how much local storage is available to them.
- Pods cannot request guaranteed local storage.
- Local storage is a best-effort resource.
- Pods can be evicted due to other pods filling the local storage, after which new pods are not admitted until sufficient storage is reclaimed.

Unlike persistent volumes, ephemeral storage is unstructured and the space is shared between all pods running on a node, in addition to other uses by the system, the container runtime, and OpenShift Dedicated. The ephemeral storage framework allows pods to specify their transient local storage needs. It also allows OpenShift Dedicated to schedule pods where appropriate, and to protect the node against excessive use of local storage.

While the ephemeral storage framework allows administrators and developers to better manage local storage, I/O throughput and latency are not directly affected.

2.2. TYPES OF EPHEMERAL STORAGE

Ephemeral local storage is always made available in the primary partition. There are two basic ways of creating the primary partition: root and runtime.

2.2.1. Root

This partition holds the kubelet root directory, `/var/lib/kubelet/` by default, and `/var/log/` directory. This partition can be shared between user pods, the OS, and Kubernetes system daemons. This partition can be consumed by pods through **EmptyDir** volumes, container logs, image layers, and container-writable layers. Kubelet manages shared access and isolation of this partition. This partition is ephemeral, and applications cannot expect any performance SLAs, such as disk IOPS, from this partition.

2.2.2. Runtime

This is an optional partition that runtimes can use for overlay file systems. OpenShift Dedicated attempts to identify and provide shared access along with isolation to this partition. Container image layers and writable layers are stored here. If the runtime partition exists, the **root** partition does not hold any image layer or other writable storage.

2.3. EPHEMERAL STORAGE MANAGEMENT

Cluster administrators can manage ephemeral storage within a project by setting quotas that define the limit ranges and number of requests for ephemeral storage across all pods in a non-terminal state. Developers can also set requests and limits on this compute resource at the pod and container level.


You can manage local ephemeral storage by specifying requests and limits. Each container in a pod can specify the following:

- `spec.containers[].resources.limits.ephemeral-storage`
- `spec.containers[].resources.requests.ephemeral-storage`

2.3.1. Ephemeral storage limits and requests units

Limits and requests for ephemeral storage are measured in byte quantities. You can express storage as a plain integer or as a fixed-point number using one of these suffixes: E, P, T, G, M, k. You can also use the power-of-two equivalents: Ei, Pi, Ti, Gi, Mi, Ki.

For example, the following quantities all represent approximately the same value: 128974848, 129e6, 129M, and 123Mi.



IMPORTANT

The suffixes for each byte quantity are case-sensitive. Be sure to use the correct case. Use the case-sensitive "M", such as used in "400M", to set the request at 400 megabytes. Use the case-sensitive "400Mi" to request 400 mebibytes. If you specify "400m" of ephemeral storage, the storage request is only 0.4 bytes.

2.3.2. Ephemeral storage requests and limits example

The following example configuration file shows a pod with two containers:

- Each container requests 2GiB of local ephemeral storage.
- Each container has a limit of 4GiB of local ephemeral storage.
- At the pod level, kubelet works out an overall pod storage limit by adding up the limits of all the containers in that pod.
 - In this case, the total storage usage at the pod level is the sum of the disk usage from all containers plus the pod's **emptyDir** volumes.
 - Therefore, the pod has a request of 4GiB of local ephemeral storage, and a limit of 8GiB of local ephemeral storage.

Example ephemeral storage configuration with quotas and limits

```
apiVersion: v1
kind: Pod
metadata:
  name: frontend
spec:
  containers:
  - name: app
    image: images.my-company.example/app:v4
    resources:
      requests:
```

```

    ephemeral-storage: "2Gi" ❶
  limits:
    ephemeral-storage: "4Gi" ❷
  volumeMounts:
  - name: ephemeral
    mountPath: "/tmp"
  - name: log-aggregator
    image: images.my-company.example/log-aggregator:v6
  resources:
    requests:
      ephemeral-storage: "2Gi"
    limits:
      ephemeral-storage: "4Gi"
  volumeMounts:
  - name: ephemeral
    mountPath: "/tmp"
  volumes:
  - name: ephemeral
    emptyDir: {}

```

❶ Container request for local ephemeral storage.

❷ Container limit for local ephemeral storage.

2.3.3. Ephemeral storage configuration effects pod scheduling and eviction

The settings in the pod spec affect both how the scheduler makes a decision about scheduling pods and when kubelet evicts pods.

- First, the scheduler ensures that the sum of the resource requests of the scheduled containers is less than the capacity of the node. In this case, the pod can be assigned to a node only if the node's available ephemeral storage (allocatable resource) is more than 4GiB.
- Second, at the container level, because the first container sets a resource limit, kubelet eviction manager measures the disk usage of this container and evicts the pod if the storage usage of the container exceeds its limit (4GiB). The kubelet eviction manager also marks the pod for eviction if the total usage exceeds the overall pod storage limit (8GiB).

2.4. MONITORING EPHEMERAL STORAGE

You can use **/bin/df** as a tool to monitor ephemeral storage usage on the volume where ephemeral container data is located, which is **/var/lib/kubelet** and **/var/lib/containers**. The available space for only **/var/lib/kubelet** is shown when you use the **df** command if **/var/lib/containers** is placed on a separate disk by the cluster administrator.

To show the human-readable values of used and available space in **/var/lib**, enter the following command:

```
$ df -h /var/lib
```

The output shows the ephemeral storage usage in **/var/lib**:

Example output

Filesystem	Size	Used	Avail	Use%	Mounted on
/dev/disk/by-partuuid/4cd1448a-01	69G	32G	34G	49%	/

CHAPTER 3. UNDERSTANDING PERSISTENT STORAGE


3.1. PERSISTENT STORAGE OVERVIEW

Managing storage is a distinct problem from managing compute resources. OpenShift Dedicated uses the Kubernetes persistent volume (PV) framework to allow cluster administrators to provision persistent storage for a cluster. Developers can use persistent volume claims (PVCs) to request PV resources without having specific knowledge of the underlying storage infrastructure.

PVCs are specific to a project, and are created and used by developers as a means to use a PV. PV resources on their own are not scoped to any single project; they can be shared across the entire OpenShift Dedicated cluster and claimed from any project. After a PV is bound to a PVC, that PV can not then be bound to additional PVCs. This has the effect of scoping a bound PV to a single namespace, that of the binding project.

PVs are defined by a **PersistentVolume** API object, which represents a piece of existing storage in the cluster that was either statically provisioned by the cluster administrator or dynamically provisioned using a **StorageClass** object. It is a resource in the cluster just like a node is a cluster resource.

PVs are volume plugins like **Volumes** but have a lifecycle that is independent of any individual pod that uses the PV. PV objects capture the details of the implementation of the storage, be that NFS, iSCSI, or a cloud-provider-specific storage system.



IMPORTANT

High availability of storage in the infrastructure is left to the underlying storage provider.

PVCs are defined by a **PersistentVolumeClaim** API object, which represents a request for storage by a developer. It is similar to a pod in that pods consume node resources and PVCs consume PV resources. For example, pods can request specific levels of resources, such as CPU and memory, while PVCs can request specific storage capacity and access modes. For example, they can be mounted once read-write or many times read-only.

3.2. LIFECYCLE OF A VOLUME AND CLAIM

PVs are resources in the cluster. PVCs are requests for those resources and also act as claim checks to the resource. The interaction between PVs and PVCs have the following lifecycle.

3.2.1. Provision storage

In response to requests from a developer defined in a PVC, a cluster administrator configures one or more dynamic provisioners that provision storage and a matching PV.

3.2.2. Bind claims

When you create a PVC, you request a specific amount of storage, specify the required access mode, and create a storage class to describe and classify the storage. The control loop in the master watches for new PVCs and binds the new PVC to an appropriate PV. If an appropriate PV does not exist, a provisioner for the storage class creates one.

The size of all PVs might exceed your PVC size. This is especially true with manually provisioned PVs. To minimize the excess, OpenShift Dedicated binds to the smallest PV that matches all other criteria.

Claims remain unbound indefinitely if a matching volume does not exist or can not be created with any available provisioner servicing a storage class. Claims are bound as matching volumes become available. For example, a cluster with many manually provisioned 50Gi volumes would not match a PVC requesting 100Gi. The PVC can be bound when a 100Gi PV is added to the cluster.

3.2.3. Use pods and claimed PVs

Pods use claims as volumes. The cluster inspects the claim to find the bound volume and mounts that volume for a pod. For those volumes that support multiple access modes, you must specify which mode applies when you use the claim as a volume in a pod.

Once you have a claim and that claim is bound, the bound PV belongs to you for as long as you need it. You can schedule pods and access claimed PVs by including **persistentVolumeClaim** in the pod's volumes block.



NOTE

If you attach persistent volumes that have high file counts to pods, those pods can fail or can take a long time to start. For more information, see [When using Persistent Volumes with high file counts in OpenShift, why do pods fail to start or take an excessive amount of time to achieve "Ready" state?](#).


3.2.4. Release a persistent volume

When you are finished with a volume, you can delete the PVC object from the API, which allows reclamation of the resource. The volume is considered released when the claim is deleted, but it is not yet available for another claim. The previous claimant's data remains on the volume and must be handled according to policy.

3.2.5. Reclaim policy for persistent volumes

The reclaim policy of a persistent volume tells the cluster what to do with the volume after it is released. A volume's reclaim policy can be **Retain**, **Recycle**, or **Delete**.

- **Retain** reclaim policy allows manual reclamation of the resource for those volume plugins that support it.
- **Recycle** reclaim policy recycles the volume back into the pool of unbound persistent volumes once it is released from its claim.



IMPORTANT

The **Recycle** reclaim policy is deprecated in OpenShift Dedicated 4. Dynamic provisioning is recommended for equivalent and better functionality.

- **Delete** reclaim policy deletes both the **PersistentVolume** object from OpenShift Dedicated and the associated storage asset in external infrastructure, such as Amazon Elastic Block Store (Amazon EBS) or VMware vSphere.



NOTE

Dynamically provisioned volumes are always deleted.

3.2.6. Reclaiming a persistent volume manually

When a persistent volume claim (PVC) is deleted, the persistent volume (PV) still exists and is considered "released". However, the PV is not yet available for another claim because the data of the previous claimant remains on the volume.

Procedure

To manually reclaim the PV as a cluster administrator:

1. Delete the PV by running the following command:

```
$ oc delete pv <pv_name>
```

The associated storage asset in the external infrastructure, such as an AWS EBS or GCE PD volume, still exists after the PV is deleted.

2. Clean up the data on the associated storage asset.
3. Delete the associated storage asset. Alternately, to reuse the same storage asset, create a new PV with the storage asset definition.

The reclaimed PV is now available for use by another PVC.

3.2.7. Changing the reclaim policy of a persistent volume

To change the reclaim policy of a persistent volume:

1. List the persistent volumes in your cluster:

```
$ oc get pv
```

Example output

NAME	CAPACITY	ACCESSMODES	RECLAIMPOLICY	STATUS
CLAIM	STORAGECLASS	REASON	AGE	
pvc-b6efd8da-b7b5-11e6-9d58-0ed433a7dd94	4Gi	RWO	Delete	Bound
default/claim1	manual	10s		
pvc-b95650f8-b7b5-11e6-9d58-0ed433a7dd94	4Gi	RWO	Delete	Bound
default/claim2	manual	6s		
pvc-bb3ca71d-b7b5-11e6-9d58-0ed433a7dd94	4Gi	RWO	Delete	Bound
default/claim3	manual	3s		

2. Choose one of your persistent volumes and change its reclaim policy:

```
$ oc patch pv <your-pv-name> -p '{"spec":{"persistentVolumeReclaimPolicy":"Retain"}}'
```

3. Verify that your chosen persistent volume has the right policy:

```
$ oc get pv
```

Example output

NAME	CAPACITY	ACCESSMODES	RECLAIMPOLICY	STATUS
------	----------	-------------	---------------	--------

CLAIM	STORAGECLASS	REASON	AGE				
pvc-b6efd8da-b7b5-11e6-9d58-0ed433a7dd94	4Gi	RWO	Delete	Bound			
default/claim1	manual	10s					
pvc-b95650f8-b7b5-11e6-9d58-0ed433a7dd94	4Gi	RWO	Delete	Bound			
default/claim2	manual	6s					
pvc-bb3ca71d-b7b5-11e6-9d58-0ed433a7dd94	4Gi	RWO	Retain	Bound			
default/claim3	manual	3s					

In the preceding output, the volume bound to claim **default/claim3** now has a **Retain** reclaim policy. The volume will not be automatically deleted when a user deletes claim **default/claim3**.

3.3. PERSISTENT VOLUMES

Each PV contains a **spec** and **status**, which is the specification and status of the volume, for example:

PersistentVolume object definition example

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: pv0001 ❶
spec:
  capacity:
    storage: 5Gi ❷
  accessModes:
    - ReadWriteOnce ❸
  persistentVolumeReclaimPolicy: Retain ❹
  ...
status:
  ...
```

- ❶ Name of the persistent volume.
- ❷ The amount of storage available to the volume.
- ❸ The access mode, defining the read-write and mount permissions.
- ❹ The reclaim policy, indicating how the resource should be handled once it is released.

You can view the name of a PVC that is bound to a PV by running the following command:

```
$ oc get pv <pv_name> -o jsonpath='{.spec.claimRef.name}'
```

3.3.1. Types of PVs

OpenShift Dedicated supports the following persistent volume plugins:

- AWS Elastic Block Store (EBS), which is installed by default.
- GCP Persistent Disk
- GCP Filestore

3.3.2. Capacity

Generally, a persistent volume (PV) has a specific storage capacity. This is set by using the **capacity** attribute of the PV.

Currently, storage capacity is the only resource that can be set or requested. Future attributes may include IOPS, throughput, and so on.


3.3.3. Access modes

A persistent volume can be mounted on a host in any way supported by the resource provider. Providers have different capabilities and each PV's access modes are set to the specific modes supported by that particular volume. For example, NFS can support multiple read-write clients, but a specific NFS PV might be exported on the server as read-only. Each PV gets its own set of access modes describing that specific PV's capabilities.

Claims are matched to volumes with similar access modes. The only two matching criteria are access modes and size. A claim's access modes represent a request. Therefore, you might be granted more, but never less. For example, if a claim requests RWO, but the only volume available is an NFS PV (RWO+ROX+RWX), the claim would then match NFS because it supports RWO.

Direct matches are always attempted first. The volume's modes must match or contain more modes than you requested. The size must be greater than or equal to what is expected. If two types of volumes, such as NFS and iSCSI, have the same set of access modes, either of them can match a claim with those modes. There is no ordering between types of volumes and no way to choose one type over another.

All volumes with the same modes are grouped, and then sorted by size, smallest to largest. The binder gets the group with matching modes and iterates over each, in size order, until one size matches.



IMPORTANT

Volume access modes describe volume capabilities. They are not enforced constraints. The storage provider is responsible for runtime errors resulting from invalid use of the resource. Errors in the provider show up at runtime as mount errors.

The following table lists the access modes:

Table 3.1. Access modes

Access Mode	CLI abbreviation	Description
ReadWriteOnce	RWO	The volume can be mounted as read-write by a single node.
ReadWriteOncePod ^[1]	RWOP	The volume can be mounted as read-write by a single pod on a single node.

1. RWOP uses the SELinux mount feature. This feature is driver dependent, and enabled by default in AWS EBS and Red Hat OpenShift Data Foundation. For third-party drivers, contact your storage vendor.

Table 3.2. Supported access modes for persistent volumes

Volume plugin	ReadWriteOnce [1]	ReadWriteOncePod	ReadOnlyMany	ReadWriteMany
AWS EBS [2]	■	■		
AWS EFS	■	■	■	■
GCP Persistent Disk	■ [4]	■	■	■ [4]
GCP Filestore	■	■	■	■
LVM Storage	■	■		

1. ReadWriteOnce (RWO) volumes cannot be mounted on multiple nodes. If a node fails, the system does not allow the attached RWO volume to be mounted on a new node because it is already assigned to the failed node. If you encounter a multi-attach error message as a result, force delete the pod on a shutdown or crashed node to avoid data loss in critical workloads, such as when dynamic persistent volumes are attached.
2. Use a recreate deployment strategy for pods that rely on AWS EBS.
3. Only raw block volumes support the **ReadWriteMany** (RWX) access mode for Fibre Channel and iSCSI. For more information, see "Block volume support".
4. For GCP hyperdisk-balanced disks:
 - The supported access modes are:
 - **ReadWriteOnce**
 - **ReadWriteMany**
 - Cloning and snapshotting is disabled for disks with **ReadWriteMany** access mode enabled.
 - You can attach a single hyperdisk-balanced disk volume in **ReadWriteMany** to a maximum of 8 instances.
 - You can only resize a disk in **ReadWriteMany** if you detach the disk from all instances.
 - [Additional limitations](#).

3.3.4. Phase

Volumes can be found in one of the following phases:

Table 3.3. Volume phases

Phase	Description
Available	A free resource not yet bound to a claim.
Bound	The volume is bound to a claim.
Released	The claim was deleted, but the resource is not yet reclaimed by the cluster.
Failed	The volume has failed its automatic reclamation.

3.3.4.1. Last phase transition time

The **LastPhaseTransitionTime** field has a timestamp that updates every time a persistent volume (PV) transitions to a different phase (**pv.Status.Phase**). To find the time of the last phase transition for a PV, run the following command:

```
$ oc get pv <pv_name> -o json | jq '.status.lastPhaseTransitionTime' ❶
```

- ❶ Specify the name of the PV that you want to see the last phase transition.

3.3.4.2. Mount options

You can specify mount options while mounting a PV by using the attribute **mountOptions**.

For example:

Mount options example

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: pv0001
spec:
  capacity:
    storage: 1Gi
  accessModes:
    - ReadWriteOnce
  mountOptions: ❶
    - nfsvers=4.1
  nfs:
    path: /tmp
    server: 172.17.0.2
  persistentVolumeReclaimPolicy: Retain
  claimRef:
    name: claim1
    namespace: default
```

- ❶ Specified mount options are used while mounting the PV to the disk.

The following PV types support mount options:

- AWS Elastic Block Store (EBS)
- AWS Elastic File Storage (EFS)
- GCE Persistent Disk

3.4. PERSISTENT VOLUME CLAIMS

Each **PersistentVolumeClaim** object contains a **spec** and **status**, which is the specification and status of the persistent volume claim (PVC), for example:

PersistentVolumeClaim object definition example

```
kind: PersistentVolumeClaim
apiVersion: v1
metadata:
  name: myclaim ❶
spec:
  accessModes:
    - ReadWriteOnce ❷
  resources:
    requests:
      storage: 8Gi ❸
  storageClassName: gold ❹
status:
  ...
```

- ❶ Name of the PVC.
- ❷ The access mode, defining the read-write and mount permissions.
- ❸ The amount of storage available to the PVC.
- ❹ Name of the **StorageClass** required by the claim.

3.4.1. Storage classes

Claims can optionally request a specific storage class by specifying the storage class's name in the **storageClassName** attribute. Only PVs of the requested class, ones with the same **storageClassName** as the PVC, can be bound to the PVC. The cluster administrator can configure dynamic provisioners to service one or more storage classes. The cluster administrator can create a PV on demand that matches the specifications in the PVC.



IMPORTANT

The Cluster Storage Operator might install a default storage class depending on the platform in use. This storage class is owned and controlled by the Operator. It cannot be deleted or modified beyond defining annotations and labels. If different behavior is desired, you must define a custom storage class.

The cluster administrator can also set a default storage class for all PVCs. When a default storage class is configured, the PVC must explicitly ask for **StorageClass** or **storageClassName** annotations set to "" to be bound to a PV without a storage class.



NOTE

If more than one storage class is marked as default, a PVC can only be created if the **storageClassName** is explicitly specified. Therefore, only one storage class should be set as the default.

3.4.2. Access modes

Claims use the same conventions as volumes when requesting storage with specific access modes.

3.4.3. Resources

Claims, such as pods, can request specific quantities of a resource. In this case, the request is for storage. The same resource model applies to volumes and claims.

3.4.4. Claims as volumes

Pods access storage by using the claim as a volume. Claims must exist in the same namespace as the pod using the claim. The cluster finds the claim in the pod's namespace and uses it to get the **PersistentVolume** backing the claim. The volume is mounted to the host and into the pod, for example:


Mount volume to the host and into the pod example

```
kind: Pod
apiVersion: v1
metadata:
  name: mypod
spec:
  containers:
    - name: myfrontend
      image: dockerfile/nginx
      volumeMounts:
        - mountPath: "/var/www/html" ❶
          name: mypd ❷
  volumes:
    - name: mypd
      persistentVolumeClaim:
        claimName: myclaim ❸
```

- ❶ Path to mount the volume inside the pod.
- ❷ Name of the volume to mount. Do not mount to the container root, /, or any path that is the same in the host and the container. This can corrupt your host system if the container is sufficiently privileged, such as the host **/dev/pts** files. It is safe to mount the host by using **/host**.
- ❸ Name of the PVC, that exists in the same namespace, to use.

3.4.5. Viewing PVC usage statistics

You can view usage statistics for persistent volume claims (PVCs).



IMPORTANT

PVC usage statistics command is a Technology Preview feature only. Technology Preview features are not supported with Red Hat production service level agreements (SLAs) and might not be functionally complete. Red Hat does not recommend using them in production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process.

For more information about the support scope of Red Hat Technology Preview features, see [Technology Preview Features Support Scope](#).

3.4.5.1. User permissions required to view PVC usage statistics

To view PVC usage statistics, you must have the necessary privileges.

To log on with the necessary privileges:

- If you have admin privileges, log on as an admin.
- If you do *not* have admin privileges:
 1. Create and add cluster roles to the user by running the following commands:

```
$ oc create clusterrole routes-view --verb=get,list --resource=routes
$ oc adm policy add-cluster-role-to-user routes-view <user-name> 1
$ oc adm policy add-cluster-role-to-user cluster-monitoring-view <user-name> 2
```

1 **2** The user's name.

3.4.5.2. Viewing PVC usage statistics

- To view statistics across a cluster, run the following command:

```
$ oc adm top pvc -A
```

Example command output

```
NAMESPACE  NAME      USAGE(%)
namespace-1 data-etcd-1 3.82%
namespace-1 data-etcd-0 3.81%
namespace-1 data-etcd-2 3.81%
namespace-2 mypvc-fs-gp3 0.00%
default    mypvc-fs   98.36%
```

- To view PVC usage statistics for a specified namespace, run the following command:

```
$ oc adm top pvc -n <namespace-name> 1
```

1 Where **<namespace-name>** is the name of the specified namespace.

Example command output

```

NAMESPACE  NAME      USAGE(%)
namespace-1 data-etcd-2 3.81% 1
namespace-1 data-etcd-0 3.81%
namespace-1 data-etcd-1 3.82%

```

1 In this example, the specified namespace is **namespace-1**.

- To view usage statistics for a specified PVC and for a specified namespace, run the following command:

```
$ oc adm top pvc <pvc-name> -n <namespace-name> 1
```

1 Where **<pvc-name>** is the name of specified PVC and **<namespace-name>** is the name of the specified namespace.

Example command output

```

NAMESPACE  NAME      USAGE(%)
namespace-1 data-etcd-0 3.81% 1

```

1 In this example, the specified namespace is **namespace-1** and the specified PVC is **data-etcd-0**.

3.5. BLOCK VOLUME SUPPORT

OpenShift Dedicated can statically provision raw block volumes. These volumes do not have a file system, and can provide performance benefits for applications that either write to the disk directly or implement their own storage service.

Raw block volumes are provisioned by specifying **volumeMode: Block** in the PV and PVC specification.



IMPORTANT

Pods using raw block volumes must be configured to allow privileged containers.

The following table displays which volume plugins support block volumes.

Table 3.4. Block volume support

Volume Plugin	Manually provisioned	Dynamically provisioned	Fully supported
Amazon Elastic Block Store (Amazon EBS)	■	■	■

Volume Plugin	Manually provisioned	Dynamically provisioned	Fully supported
Amazon Elastic File Storage (Amazon EFS)			
GCP	■	■	■
LVM Storage	■	■	■

3.5.1. Block volume examples

PV example

```

apiVersion: v1
kind: PersistentVolume
metadata:
  name: block-pv
spec:
  capacity:
    storage: 10Gi
  accessModes:
    - ReadWriteOnce
  volumeMode: Block 1
  persistentVolumeReclaimPolicy: Retain
  fc:
    targetWWNs: ["50060e801049cfd1"]
    lun: 0
    readOnly: false

```

1 **volumeMode** must be set to **Block** to indicate that this PV is a raw block volume.

PVC example

```

apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: block-pvc
spec:
  accessModes:
    - ReadWriteOnce
  volumeMode: Block 1
  resources:
    requests:
      storage: 10Gi

```

1 **volumeMode** must be set to **Block** to indicate that a raw block PVC is requested.

Pod specification example

-

```

apiVersion: v1
kind: Pod
metadata:
  name: pod-with-block-volume
spec:
  containers:
    - name: fc-container
      image: fedora:26
      command: ["/bin/sh", "-c"]
      args: [ "tail -f /dev/null" ]
      volumeDevices: ❶
        - name: data
          devicePath: /dev/xvda ❷
  volumes:
    - name: data
      persistentVolumeClaim:
        claimName: block-pvc ❸

```

- ❶ **volumeDevices**, instead of **volumeMounts**, is used for block devices. Only **PersistentVolumeClaim** sources can be used with raw block volumes.
- ❷ **devicePath**, instead of **mountPath**, represents the path to the physical device where the raw block is mapped to the system.
- ❸ The volume source must be of type **persistentVolumeClaim** and must match the name of the PVC as expected.


Table 3.5. Accepted values for **volumeMode**

Value	Default
Filesystem	Yes
Block	No

Table 3.6. Binding scenarios for block volumes

PV volumeMode	PVC volumeMode	Binding result
Filesystem	Filesystem	Bind
Unspecified	Unspecified	Bind
Filesystem	Unspecified	Bind
Unspecified	Filesystem	Bind
Block	Block	Bind

PV volumeMode	PVC volumeMode	Binding result
Unspecified	Block	No Bind
Block	Unspecified	No Bind
Filesystem	Block	No Bind
Block	Filesystem	No Bind



IMPORTANT

Unspecified values result in the default value of **Filesystem**.

3.6. USING FSGROUP TO REDUCE POD TIMEOUTS

If a storage volume contains many files (~1,000,000 or greater), you may experience pod timeouts.

This can occur because, by default, OpenShift Dedicated recursively changes ownership and permissions for the contents of each volume to match the **fsGroup** specified in a pod's **securityContext** when that volume is mounted. For large volumes, checking and changing ownership and permissions can be time consuming, slowing pod startup. You can use the **fsGroupChangePolicy** field inside a **securityContext** to control the way that OpenShift Dedicated checks and manages ownership and permissions for a volume.

fsGroupChangePolicy defines behavior for changing ownership and permission of the volume before being exposed inside a pod. This field only applies to volume types that support **fsGroup**-controlled ownership and permissions. This field has two possible values:

- **OnRootMismatch**: Only change permissions and ownership if permission and ownership of root directory does not match with expected permissions of the volume. This can help shorten the time it takes to change ownership and permission of a volume to reduce pod timeouts.
- **Always**: Always change permission and ownership of the volume when a volume is mounted.

fsGroupChangePolicy example

```
securityContext:
  runAsUser: 1000
  runAsGroup: 3000
  fsGroup: 2000
  fsGroupChangePolicy: "OnRootMismatch" 1
...
```

- 1 OnRootMismatch** specifies skipping recursive permission change, thus helping to avoid pod timeout problems.

**NOTE**

The `fsGroupChangePolicy` field has no effect on ephemeral volume types, such as `secret`, `configMap`, and `emptydir`.

CHAPTER 4. CONFIGURING PERSISTENT STORAGE

4.1. PERSISTENT STORAGE USING AWS ELASTIC BLOCK STORE

OpenShift Dedicated clusters are prebuilt with two storage classes that use Amazon Elastic Block Store (Amazon EBS) volumes. These storage classes are ready to use and some familiarity with Kubernetes and AWS is assumed.

The following are the two prebuilt storage classes:

Name	Provisioner
gp2-csi	ebs.csi.aws.com
gp3-csi (default)	ebs.csi.aws.com

The gp3-csi storage class is set as default; however, you can select any of the storage classes as the default storage class.

The Kubernetes persistent volume framework allows administrators to provision a cluster with persistent storage and gives users a way to request those resources without having any knowledge of the underlying infrastructure. You can dynamically provision Amazon EBS volumes. Persistent volumes are not bound to a single project or namespace; they can be shared across the OpenShift Dedicated cluster. Persistent volume claims are specific to a project or namespace and can be requested by users. You can define a KMS key to encrypt container-persistent volumes on AWS. By default, newly created clusters using OpenShift Dedicated version 4.10 and later use gp3 storage and the [AWS EBS CSI driver](#).



IMPORTANT

High-availability of storage in the infrastructure is left to the underlying storage provider.

4.1.1. Creating the EBS storage class

Storage classes are used to differentiate and delineate storage levels and usages. By defining a storage class, users can obtain dynamically provisioned persistent volumes.

4.1.2. Creating the persistent volume claim

Prerequisites

Storage must exist in the underlying infrastructure before it can be mounted as a volume in OpenShift Dedicated.

Procedure

1. In the OpenShift Dedicated web console, click **Storage → Persistent Volume Claims**
2. In the persistent volume claims overview, click **Create Persistent Volume Claim**
3. Define the desired options on the page that appears.
 - a. Select the previously-created storage class from the drop-down menu.

- b. Enter a unique name for the storage claim.
 - c. Select the access mode. This selection determines the read and write access for the storage claim.
 - d. Define the size of the storage claim.
4. Click **Create** to create the persistent volume claim and generate a persistent volume.

4.1.3. Volume format

Before OpenShift Dedicated mounts the volume and passes it to a container, it checks that the volume contains a file system as specified by the **fsType** parameter in the persistent volume definition. If the device is not formatted with the file system, all data from the device is erased and the device is automatically formatted with the given file system.

This verification enables you to use unformatted AWS volumes as persistent volumes, because OpenShift Dedicated formats them before the first use.

4.1.4. Maximum number of EBS volumes on a node

By default, OpenShift Dedicated supports a maximum of 39 EBS volumes attached to one node. This limit is consistent with the [AWS volume limits](#). The volume limit depends on the instance type.



IMPORTANT

As a cluster administrator, you must use either in-tree or Container Storage Interface (CSI) volumes and their respective storage classes, but never both volume types at the same time. The maximum attached EBS volume number is counted separately for in-tree and CSI volumes, which means you could have up to 39 EBS volumes of each type.

For information about accessing additional storage options, such as volume snapshots, that are not possible with in-tree volume plug-ins, see [AWS Elastic Block Store CSI Driver Operator](#).

4.1.5. Encrypting container persistent volumes on AWS with a KMS key

Defining a KMS key to encrypt container-persistent volumes on AWS is useful when you have explicit compliance and security guidelines when deploying to AWS.

Prerequisites

- Underlying infrastructure must contain storage.
- You must create a customer KMS key on AWS.

Procedure

1. Create a storage class:

```
$ cat << EOF | oc create -f -
apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
  name: <storage-class-name> 1
```

```
parameters:
  fsType: ext4 2
  encrypted: "true"
  kmsKeyId: keyvalue 3
  provisioner: ebs.csi.aws.com
  reclaimPolicy: Delete
  volumeBindingMode: WaitForFirstConsumer
EOF
```

- 1 Specifies the name of the storage class.
- 2 File system that is created on provisioned volumes.
- 3 Specifies the full Amazon Resource Name (ARN) of the key to use when encrypting the container-persistent volume. If you do not provide any key, but the **encrypted** field is set to **true**, then the default KMS key is used. See [Finding the key ID and key ARN on AWS](#) in the AWS documentation.

2. Create a persistent volume claim (PVC) with the storage class specifying the KMS key:

```
$ cat << EOF | oc create -f -
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: mypvc
spec:
  accessModes:
    - ReadWriteOnce
  volumeMode: Filesystem
  storageClassName: <storage-class-name>
resources:
  requests:
    storage: 1Gi
EOF
```

3. Create workload containers to consume the PVC:

```
$ cat << EOF | oc create -f -
kind: Pod
metadata:
  name: mypod
spec:
  containers:
    - name: httpd
      image: quay.io/centos7/httpd-24-centos7
      ports:
        - containerPort: 80
      volumeMounts:
        - mountPath: /mnt/storage
          name: data
  volumes:
    - name: data
      persistentVolumeClaim:
        claimName: mypvc
EOF
```



4.1.6. Additional resources

- See [AWS Elastic Block Store CSI Driver Operator](#) for information about accessing additional storage options, such as volume snapshots, that are not possible with in-tree volume plugins.

4.2. PERSISTENT STORAGE USING GCE PERSISTENT DISK

OpenShift Dedicated supports GCE Persistent Disk volumes (gcePD). You can provision your OpenShift Dedicated cluster with persistent storage using GCE. Some familiarity with Kubernetes and GCE is assumed.

The Kubernetes persistent volume framework allows administrators to provision a cluster with persistent storage and gives users a way to request those resources without having any knowledge of the underlying infrastructure.

GCE Persistent Disk volumes can be provisioned dynamically.

Persistent volumes are not bound to a single project or namespace; they can be shared across the OpenShift Dedicated cluster. Persistent volume claims are specific to a project or namespace and can be requested by users.



IMPORTANT

High availability of storage in the infrastructure is left to the underlying storage provider.

Additional resources

- [GCE Persistent Disk](#)

4.2.1. Creating the GCE storage class

Storage classes are used to differentiate and delineate storage levels and usages. By defining a storage class, users can obtain dynamically provisioned persistent volumes.

4.2.2. Creating the persistent volume claim

Prerequisites

Storage must exist in the underlying infrastructure before it can be mounted as a volume in OpenShift Dedicated.

Procedure

1. In the OpenShift Dedicated web console, click **Storage → Persistent Volume Claims**
2. In the persistent volume claims overview, click **Create Persistent Volume Claim**
3. Define the desired options on the page that appears.
 - a. Select the previously-created storage class from the drop-down menu.
 - b. Enter a unique name for the storage claim.

- c. Select the access mode. This selection determines the read and write access for the storage claim.
 - d. Define the size of the storage claim.
4. Click **Create** to create the persistent volume claim and generate a persistent volume.

4.2.3. Volume format

Before OpenShift Dedicated mounts the volume and passes it to a container, it checks that the volume contains a file system as specified by the **fsType** parameter in the persistent volume definition. If the device is not formatted with the file system, all data from the device is erased and the device is automatically formatted with the given file system.

This verification enables you to use unformatted GCE volumes as persistent volumes, because OpenShift Dedicated formats them before the first use.

CHAPTER 5. USING CONTAINER STORAGE INTERFACE (CSI)

5.1. CONFIGURING CSI VOLUMES

The Container Storage Interface (CSI) allows OpenShift Dedicated to consume storage from storage back ends that implement the [CSI interface](#) as persistent storage.




NOTE

OpenShift Dedicated 4 supports version 1.6.0 of the [CSI specification](#).

5.1.1. CSI architecture

CSI drivers are typically shipped as container images. These containers are not aware of OpenShift Dedicated where they run. To use CSI-compatible storage back end in OpenShift Dedicated, the cluster administrator must deploy several components that serve as a bridge between OpenShift Dedicated and the storage driver.

The following diagram provides a high-level overview about the components running in pods in the OpenShift Dedicated cluster.



It is possible to run multiple CSI drivers for different storage back ends. Each driver needs its own external controllers deployment and daemon set with the driver and CSI registrar.

5.1.1.1. External CSI controllers

External CSI controllers is a deployment that deploys one or more pods with five containers:

- The snapshotter container watches **VolumeSnapshot** and **VolumeSnapshotContent** objects and is responsible for the creation and deletion of **VolumeSnapshotContent** object.

- The resizer container is a sidecar container that watches for **PersistentVolumeClaim** updates and triggers **ControllerExpandVolume** operations against a CSI endpoint if you request more storage on **PersistentVolumeClaim** object.
- An external CSI attacher container translates **attach** and **detach** calls from OpenShift Dedicated to respective **ControllerPublish** and **ControllerUnpublish** calls to the CSI driver.
- An external CSI provisioner container that translates **provision** and **delete** calls from OpenShift Dedicated to respective **CreateVolume** and **DeleteVolume** calls to the CSI driver.
- A CSI driver container.

The CSI attacher and CSI provisioner containers communicate with the CSI driver container using UNIX Domain Sockets, ensuring that no CSI communication leaves the pod. The CSI driver is not accessible from outside of the pod.



NOTE

The **attach**, **detach**, **provision**, and **delete** operations typically require the CSI driver to use credentials to the storage backend. Run the CSI controller pods on infrastructure nodes so the credentials are never leaked to user processes, even in the event of a catastrophic security breach on a compute node.



NOTE

The external attacher must also run for CSI drivers that do not support third-party **attach** or **detach** operations. The external attacher will not issue any **ControllerPublish** or **ControllerUnpublish** operations to the CSI driver. However, it still must run to implement the necessary OpenShift Dedicated attachment API.

5.1.1.2. CSI driver daemon set

The CSI driver daemon set runs a pod on every node that allows OpenShift Dedicated to mount storage provided by the CSI driver to the node and use it in user workloads (pods) as persistent volumes (PVs). The pod with the CSI driver installed contains the following containers:

- A CSI driver registrar, which registers the CSI driver into the **openshift-node** service running on the node. The **openshift-node** process running on the node then directly connects with the CSI driver using the UNIX Domain Socket available on the node.
- A CSI driver.

The CSI driver deployed on the node should have as few credentials to the storage back end as possible. OpenShift Dedicated will only use the node plugin set of CSI calls such as **NodePublish/NodeUnpublish** and **NodeStage/NodeUnstage**, if these calls are implemented.

5.1.2. CSI drivers supported by OpenShift Dedicated

OpenShift Dedicated installs certain CSI drivers by default, giving users storage options that are not possible with in-tree volume plugins.

To create CSI-provisioned persistent volumes that mount to these supported storage assets, OpenShift Dedicated installs the necessary CSI driver Operator, the CSI driver, and the required storage class by default. For more details about the default namespace of the Operator and driver, see the

documentation for the specific CSI Driver Operator.



IMPORTANT

The AWS EFS and GCP Filestore CSI drivers are not installed by default, and must be installed manually. For instructions on installing the AWS EFS CSI driver, see [Setting up AWS Elastic File Service CSI Driver Operator](#). For instructions on installing the GCP Filestore CSI driver, see [Google Compute Platform Filestore CSI Driver Operator](#).

The following table describes the CSI drivers that are supported by OpenShift Dedicated, and which CSI features they support, such as volume snapshots and resize.



IMPORTANT

If your CSI driver is not listed in the following table, you must follow the installation instructions provided by your CSI storage vendor to use their supported CSI features.

For a list of third-party-certified CSI drivers, see the *Red Hat ecosystem portal* under *Additional resources*.

Table 5.1. Supported CSI drivers and features in OpenShift Dedicated

CSI driver	CSI volume snapshots	CSI volume group snapshots [1]	CSI cloning	CSI resize	Inline ephemeral volumes
AWS EBS	■			■	
AWS EFS					
Google Compute Platform (GCP) persistent disk (PD)	■		■ [2]	■	
GCP Filestore	■			■	
LVM Storage	■		■	■	

Additional resources

- [Red Hat ecosystem portal](#)
- [Third-party support policy](#)

5.1.3. Dynamic provisioning

Dynamic provisioning of persistent storage depends on the capabilities of the CSI driver and underlying storage back end. The provider of the CSI driver should document how to create a storage class in OpenShift Dedicated and the parameters available for configuration.

The created storage class can be configured to enable dynamic provisioning.

Procedure

- Create a default storage class that ensures all PVCs that do not require any special storage class are provisioned by the installed CSI driver.

```
# oc create -f - << EOF
apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
  name: <storage-class> 1
  annotations:
    storageclass.kubernetes.io/is-default-class: "true"
provisioner: <provisioner-name> 2
parameters:
  csi.storage.k8s.io/fstype: xfs 3
EOF
```

- 1 The name of the storage class that will be created.
- 2 The name of the CSI driver that has been installed.
- 3 The vSphere CSI driver supports all of the file systems supported by the underlying Red Hat Core operating system release, including XFS and Ext4.

5.1.4. Example using the CSI driver

The following example installs a default MySQL template without any changes to the template.

Prerequisites

- The CSI driver has been deployed.
- A storage class has been created for dynamic provisioning.

Procedure

- Create the MySQL template:

```
# oc new-app mysql-persistent
```

Example output

```
--> Deploying template "openshift/mysql-persistent" to project default
...
```

```
# oc get pvc
```

Example output

NAME	STATUS	VOLUME	CAPACITY
mysql	Bound	kubernetes-dynamic-pv-3271ffcb4e1811e8	1Gi
ACCESS MODES	STORAGECLASS	AGE	
RWO	gp3-csi	3s	

5.2. MANAGING THE DEFAULT STORAGE CLASS

5.2.1. Overview

Managing the default storage class allows you to accomplish several different objectives:

- Enforcing static provisioning by disabling dynamic provisioning.
- When you have other preferred storage classes, preventing the storage operator from re-creating the initial default storage class.
- Renaming, or otherwise changing, the default storage class

To accomplish these objectives, you change the setting for the **spec.storageClassState** field in the **ClusterCSIDriver** object. The possible settings for this field are:

- **Managed:** (Default) The Container Storage Interface (CSI) operator is actively managing its default storage class, so that most manual changes made by a cluster administrator to the default storage class are removed, and the default storage class is continuously re-created if you attempt to manually delete it.
- **Unmanaged:** You can modify the default storage class. The CSI operator is not actively managing storage classes, so that it is not reconciling the default storage class it creates automatically.
- **Removed:** The CSI operators deletes the default storage class.

5.2.2. Managing the default storage class using the web console

Prerequisites

- Access to the OpenShift Dedicated web console.
- Access to the cluster with cluster-admin privileges.

Procedure

To manage the default storage class using the web console:

1. Log in to the web console.
2. Click **Administration** > **CustomResourceDefinitions**.
3. On the **CustomResourceDefinitions** page, type **clustercsidriver** to find the **ClusterCSIDriver** object.
4. Click **ClusterCSIDriver**, and then click the **Instances** tab.

- Click the name of the desired instance, and then click the **YAML** tab.
- Add the **spec.storageClassState** field with a value of **Managed**, **Unmanaged**, or **Removed**.

Example

```
...
spec:
  driverConfig:
    driverType: "
  logLevel: Normal
  managementState: Managed
  observedConfig: null
  operatorLogLevel: Normal
  storageClassState: Unmanaged 1
...
```

1 **spec.storageClassState** field set to "Unmanaged"

- Click **Save**.

5.2.3. Managing the default storage class using the CLI

Prerequisites

- Access to the cluster with cluster-admin privileges.

Procedure

To manage the storage class using the CLI, run the following command:

```
$ oc patch clustercsidriver $DRIVERNAME --type=merge -p '{"spec":
{"storageClassState":"'${STATE}'"}' 1
```

1 Where **`\${STATE}`** is "Removed" or "Managed" or "Unmanaged".

Where **`\${DRIVERNAME}`** is the provisioner name. You can find the provisioner name by running the command **oc get sc**.

5.2.4. Absent or multiple default storage classes

5.2.4.1. Multiple default storage classes

Multiple default storage classes can occur if you mark a non-default storage class as default and do not unset the existing default storage class, or you create a default storage class when a default storage class is already present. With multiple default storage classes present, any persistent volume claim (PVC) requesting the default storage class (**pvc.spec.storageClassName=nil**) gets the most recently created default storage class, regardless of the default status of that storage class, and the administrator receives an alert in the alerts dashboard that there are multiple default storage classes, **MultipleDefaultStorageClasses**.

5.2.4.2. Absent default storage class

There are two possible scenarios where PVCs can attempt to use a non-existent default storage class:

- An administrator removes the default storage class or marks it as non-default, and then a user creates a PVC requesting the default storage class.
- During installation, the installer creates a PVC requesting the default storage class, which has not yet been created.

In the preceding scenarios, PVCs remain in the pending state indefinitely. To resolve this situation, create a default storage class or declare one of the existing storage classes as the default. As soon as the default storage class is created or declared, the PVCs get the new default storage class. If possible, the PVCs eventually bind to statically or dynamically provisioned PVs as usual, and move out of the pending state.

5.2.5. Changing the default storage class

Use the following procedure to change the default storage class.

For example, if you have two defined storage classes, **gp3** and **standard**, and you want to change the default storage class from **gp3** to **standard**.

Prerequisites

- Access to the cluster with cluster-admin privileges.

Procedure

To change the default storage class:

1. List the storage classes:

```
$ oc get storageclass
```

Example output

NAME	TYPE
gp3 (default)	ebs.csi.aws.com 1
standard	ebs.csi.aws.com

1 **(default)** indicates the default storage class.

2. Make the desired storage class the default.

For the desired storage class, set the **storageclass.kubernetes.io/is-default-class** annotation to **true** by running the following command:

```
$ oc patch storageclass standard -p '{"metadata": {"annotations": {"storageclass.kubernetes.io/is-default-class": "true"}}}'
```



NOTE

You can have multiple default storage classes for a short time. However, you should ensure that only one default storage class exists eventually.

With multiple default storage classes present, any persistent volume claim (PVC) requesting the default storage class (**pvc.spec.storageClassName=nil**) gets the most recently created default storage class, regardless of the default status of that storage class, and the administrator receives an alert in the alerts dashboard that there are multiple default storage classes, **MultipleDefaultStorageClasses**.

3. Remove the default storage class setting from the old default storage class.
For the old default storage class, change the value of the **storageclass.kubernetes.io/is-default-class** annotation to **false** by running the following command:

```
$ oc patch storageclass gp3 -p '{"metadata": {"annotations": {"storageclass.kubernetes.io/is-default-class": "false"}}}'
```

4. Verify the changes:

```
$ oc get storageclass
```

Example output

NAME	TYPE
gp3	ebs.csi.aws.com
standard (default)	ebs.csi.aws.com

5.3. AWS ELASTIC BLOCK STORE CSI DRIVER OPERATOR

5.3.1. Overview

OpenShift Dedicated is capable of provisioning persistent volumes (PVs) using the [AWS EBS CSI driver](#).

Familiarity with [persistent storage](#) and [configuring CSI volumes](#) is recommended when working with a Container Storage Interface (CSI) Operator and driver.

To create CSI-provisioned PVs that mount to AWS EBS storage assets, OpenShift Dedicated installs the [AWS EBS CSI Driver Operator](#) (a Red Hat operator) and the AWS EBS CSI driver by default in the **openshift-cluster-csi-drivers** namespace.

- The *AWS EBS CSI Driver Operator* provides a StorageClass by default that you can use to create PVCs. You can disable this default storage class if desired (see [Managing the default storage class](#)). You also have the option to create the AWS EBS StorageClass as described in [Persistent storage using Amazon Elastic Block Store](#).
- The *AWS EBS CSI driver* enables you to create and mount AWS EBS PVs.

5.3.2. About CSI

Storage vendors have traditionally provided storage drivers as part of Kubernetes. With the implementation of the Container Storage Interface (CSI), third-party providers can instead deliver storage plugins using a standard interface without ever having to change the core Kubernetes code.

CSI Operators give OpenShift Dedicated users storage options, such as volume snapshots, that are not possible with in-tree volume plugins.



IMPORTANT

OpenShift Dedicated defaults to using the CSI plugin to provision Amazon Elastic Block Store (Amazon EBS) storage.

For information about dynamically provisioning AWS EBS persistent volumes in OpenShift Dedicated, see [Persistent storage using Amazon Elastic Block Store](#).

Additional resources

- [Persistent storage using Amazon Elastic Block Store](#)
- [Configuring CSI volumes](#)

5.4. AWS ELASTIC FILE SERVICE CSI DRIVER OPERATOR



IMPORTANT

This procedure is specific to the [AWS EFS CSI Driver Operator](#) (a Red Hat Operator), which is only applicable for OpenShift Dedicated 4.10 and later versions.

5.4.1. Overview

OpenShift Dedicated is capable of provisioning persistent volumes (PVs) using the Container Storage Interface (CSI) driver for AWS Elastic File Service (EFS).

Familiarity with [persistent storage](#) and [configuring CSI volumes](#) is recommended when working with a CSI Operator and driver.

After installing the AWS EFS CSI Driver Operator, OpenShift Dedicated installs the AWS EFS CSI Operator and the AWS EFS CSI driver by default in the **openshift-cluster-csi-drivers** namespace. This allows the AWS EFS CSI Driver Operator to create CSI-provisioned PVs that mount to AWS EFS assets.

- The *AWS EFS CSI Driver Operator*, after being installed, does not create a storage class by default to use to create persistent volume claims (PVCs). However, you can manually create the AWS EFS **StorageClass**. The AWS EFS CSI Driver Operator supports dynamic volume provisioning by allowing storage volumes to be created on-demand. This eliminates the need for cluster administrators to pre-provision storage.
- The *AWS EFS CSI driver* enables you to create and mount AWS EFS PVs.



NOTE

AWS EFS only supports regional volumes, not zonal volumes.

5.4.2. About CSI

Storage vendors have traditionally provided storage drivers as part of Kubernetes. With the implementation of the Container Storage Interface (CSI), third-party providers can instead deliver storage plugins using a standard interface without ever having to change the core Kubernetes code.


CSI Operators give OpenShift Dedicated users storage options, such as volume snapshots, that are not possible with in-tree volume plugins.

5.4.3. Setting up the AWS EFS CSI Driver Operator

1. If you are using AWS EFS with AWS Secure Token Service (STS), obtain a role Amazon Resource Name (ARN) for STS. This is required for installing the AWS EFS CSI Driver Operator.
2. Install the AWS EFS CSI Driver Operator.
3. Install the AWS EFS CSI Driver.

5.4.3.1. Obtaining a role Amazon Resource Name for Security Token Service

This procedure explains how to obtain a role Amazon Resource Name (ARN) to configure the AWS EFS CSI Driver Operator with OpenShift Dedicated on AWS Security Token Service (STS).



IMPORTANT

Perform this procedure before you install the AWS EFS CSI Driver Operator (see *Installing the AWS EFS CSI Driver Operator* procedure).

Prerequisites

- Access to the cluster as a user with the cluster-admin role.
- AWS account credentials

Procedure

1. Create an IAM policy JSON file with the following content:

```
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Effect": "Allow",
      "Action": [
        "elasticfilesystem:DescribeAccessPoints",
        "elasticfilesystem:DescribeFileSystems",
        "elasticfilesystem:DescribeMountTargets",
        "ec2:DescribeAvailabilityZones",
        "elasticfilesystem:TagResource"
      ],
      "Resource": "*"
    },
    {
      "Effect": "Allow",
      "Action": [
        "elasticfilesystem:CreateAccessPoint"
      ],
      "Resource": "*",
      "Condition": {
        "StringLike": {
          "aws:RequestTag/efs.csi.aws.com/cluster": "true"
        }
      }
    }
  ]
}
```

```

    }
  },
  {
    "Effect": "Allow",
    "Action": "elasticfilesystem:DeleteAccessPoint",
    "Resource": "*",
    "Condition": {
      "StringEquals": {
        "aws:ResourceTag/efs.csi.aws.com/cluster": "true"
      }
    }
  }
]
}

```

2. Create an IAM trust JSON file with the following content:

```

{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Effect": "Allow",
      "Principal": {
        "Federated": "arn:aws:iam::<your_aws_account_ID>:oidc-
provider/<openshift_oidc_provider>" ❶
      },
      "Action": "sts:AssumeRoleWithWebIdentity",
      "Condition": {
        "StringEquals": {
          "<openshift_oidc_provider>:sub": [ ❷
            "system:serviceaccount:openshift-cluster-csi-drivers:aws-efs-csi-driver-operator",
            "system:serviceaccount:openshift-cluster-csi-drivers:aws-efs-csi-driver-controller-sa"
          ]
        }
      }
    }
  ]
}

```

- ❶ Specify your AWS account ID and the OpenShift OIDC provider endpoint.

Obtain your AWS account ID by running the following command:

```
$ aws sts get-caller-identity --query Account --output text
```

Obtain the OpenShift OIDC endpoint by running the following command:

```
$ openshift_oidc_provider=`oc get authentication.config.openshift.io cluster \
-o json | jq -r .spec.serviceAccountIssuer | sed -e "s/^https://"; \
echo $openshift_oidc_provider
```

- ❷ Specify the OpenShift OIDC endpoint again.

3. Create the IAM role:

```
ROLE_ARN=$(aws iam create-role \
  --role-name "<your_cluster_name>-aws-efs-csi-operator" \
  --assume-role-policy-document file://<your_trust_file_name>.json \
  --query "Role.Arn" --output text); echo $ROLE_ARN
```

Copy the role ARN. You will need it when you install the AWS EFS CSI Driver Operator.

4. Create the IAM policy:

```
POLICY_ARN=$(aws iam create-policy \
  --policy-name "<your_cluster_name>-aws-efs-csi" \
  --policy-document file://<your_policy_file_name>.json \
  --query 'Policy.Arn' --output text); echo $POLICY_ARN
```

5. Attach the IAM policy to the IAM role:

```
$ aws iam attach-role-policy \
  --role-name "<your_cluster_name>-aws-efs-csi-operator" \
  --policy-arn $POLICY_ARN
```

Next steps

[Install the AWS EFS CSI Driver Operator](#) .

Additional resources

- [Installing the AWS EFS CSI Driver Operator](#)
- [Installing the AWS EFS CSI Driver](#)

5.4.3.2. Installing the AWS EFS CSI Driver Operator

The AWS EFS CSI Driver Operator (a Red Hat Operator) is not installed in OpenShift Dedicated by default. Use the following procedure to install and configure the AWS EFS CSI Driver Operator in your cluster.


Prerequisites

- Access to the OpenShift Dedicated web console.

Procedure

To install the AWS EFS CSI Driver Operator from the web console:

1. Log in to the web console.
2. Install the AWS EFS CSI Operator:
 - a. Click **Operators** → **OperatorHub**.
 - b. Locate the AWS EFS CSI Operator by typing **AWS EFS CSI** in the filter box.
 - c. Click the **AWS EFS CSI Driver Operator** button.



IMPORTANT

Be sure to select the **AWS EFS CSI Driver Operator** and not the **AWS EFS Operator**. The **AWS EFS Operator** is a community Operator and is not supported by Red Hat.

- a. On the **AWS EFS CSI Driver Operator** page, click **Install**.
- b. On the **Install Operator** page, ensure that:
 - If you are using AWS EFS with AWS Secure Token Service (STS), in the **role ARN** field, enter the ARN role copied from the last step of the *Obtaining a role Amazon Resource Name for Security Token Service* procedure.
 - **All namespaces on the cluster (default)** is selected.
 - **Installed Namespace** is set to **openshift-cluster-csi-drivers**.
- c. Click **Install**.
After the installation finishes, the AWS EFS CSI Operator is listed in the **Installed Operators** section of the web console.

Next steps

[Install the AWS EFS CSI Driver](#) .

5.4.3.3. Installing the AWS EFS CSI Driver

After installing the [AWS EFS CSI Driver Operator](#) (a Red Hat operator), you install the [AWS EFS CSI driver](#).

Prerequisites

- Access to the OpenShift Dedicated web console.

Procedure

1. Click **Administration** → **CustomResourceDefinitions** → **ClusterCSIDriver**.
2. On the **Instances** tab, click **Create ClusterCSIDriver**.
3. Use the following YAML file:

```
apiVersion: operator.openshift.io/v1
kind: ClusterCSIDriver
metadata:
  name: efs.csi.aws.com
spec:
  managementState: Managed
```

4. Click **Create**.
5. Wait for the following Conditions to change to a "True" status:
 - AWSEFSDriverNodeServiceControllerAvailable

- AWSEFSDriverControllerServiceControllerAvailable

5.4.4. Creating the AWS EFS storage class

Storage classes are used to differentiate and delineate storage levels and usages. By defining a storage class, users can obtain dynamically provisioned persistent volumes.

The [AWS EFS CSI Driver Operator](#) (a Red Hat operator), after being installed, does not create a storage class by default. However, you can manually create the AWS EFS storage class.

5.4.4.1. Creating the AWS EFS storage class using the console

Procedure

1. In the OpenShift Dedicated web console, click **Storage** → **StorageClasses**.
2. On the **StorageClasses** page, click **Create StorageClass**.
3. On the **StorageClass** page, perform the following steps:
 - a. Enter a name to reference the storage class.
 - b. Optional: Enter the description.
 - c. Select the reclaim policy.
 - d. Select **efs.csi.aws.com** from the **Provisioner** drop-down list.
 - e. Optional: Set the configuration parameters for the selected provisioner.
4. Click **Create**.

5.4.4.2. Creating the AWS EFS storage class using the CLI

Procedure

- Create a **StorageClass** object:

```
kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: efs-sc
provisioner: efs.csi.aws.com
parameters:
  provisioningMode: efs-ap 1
  filesystemId: fs-a5324911 2
  directoryPerms: "700" 3
  gidRangeStart: "1000" 4
  gidRangeEnd: "2000" 5
  basePath: "/dynamic_provisioning" 6
```

1 **provisioningMode** must be **efs-ap** to enable dynamic provisioning.

2 **filesystemId** must be the ID of the EFS volume created manually.

- 3 **directoryPerms** is the default permission of the root directory of the volume. In this example, the volume is accessible only by the owner.
- 4 5 **gidRangeStart** and **gidRangeEnd** set the range of POSIX Group IDs (GIDs) that are used to set the GID of the AWS access point. If not specified, the default range is 50000–7000000. Each provisioned volume, and thus AWS access point, is assigned a unique GID from this range.
- 6 **basePath** is the directory on the EFS volume that is used to create dynamically provisioned volumes. In this case, a PV is provisioned as `"/dynamic_provisioning/<random uuid>"` on the EFS volume. Only the subdirectory is mounted to pods that use the PV.



NOTE

A cluster admin can create several **StorageClass** objects, each using a different EFS volume.

5.4.5. AWS EFS CSI cross account support

Cross account support allows you to have an OpenShift Dedicated cluster in one AWS account and mount your file system in another AWS account by using the AWS Elastic File System (EFS) Container Storage Interface (CSI) driver.

Prerequisites

- Access to an OpenShift Dedicated cluster with administrator rights
- Two valid AWS accounts
- The EFS CSI Operator has been installed. For information about installing the EFS CSI Operator, see the *Installing the AWS EFS CSI Driver Operator* section.
- Both the OpenShift Dedicated cluster and EFS file system must be located in the same AWS region.
- Ensure that the two virtual private clouds (VPCs) used in the following procedure use different network Classless Inter-Domain Routing (CIDR) ranges.
- Access to OpenShift Dedicated CLI (**oc**).
- Access to AWS CLI.
- Access to **jq** command-line JSON processor.

Procedure

The following procedure explains how to set up:

- OpenShift Dedicated AWS Account A: Contains a Red Hat OpenShift Dedicated cluster v4.16, or later, deployed within a VPC
- AWS Account B: Contains a VPC (including subnets, route tables, and network connectivity). The EFS filesystem will be created in this VPC.

To use AWS EFS across accounts:

1. Set up the environment:

a. Configure environment variables by running the following commands:

```
export CLUSTER_NAME="<CLUSTER_NAME>" 1
export AWS_REGION="<AWS_REGION>" 2
export AWS_ACCOUNT_A_ID="<ACCOUNT_A_ID>" 3
export AWS_ACCOUNT_B_ID="<ACCOUNT_B_ID>" 4
export AWS_ACCOUNT_A_VPC_CIDR="<VPC_A_CIDR>" 5
export AWS_ACCOUNT_B_VPC_CIDR="<VPC_B_CIDR>" 6
export AWS_ACCOUNT_A_VPC_ID="<VPC_A_ID>" 7
export AWS_ACCOUNT_B_VPC_ID="<VPC_B_ID>" 8
export SCRATCH_DIR="<WORKING_DIRECTORY>" 9
export CSI_DRIVER_NAMESPACE="openshift-cluster-csi-drivers" 10
export AWS_PAGER="" 11
```

- 1** Cluster name of choice.
- 2** AWS region of choice.
- 3** AWS Account A ID.
- 4** AWS Account B ID.
- 5** CIDR range of VPC in Account A.
- 6** CIDR range of VPC in Account B.
- 7** VPC ID in Account A (cluster)
- 8** VPC ID in Account B (EFS cross account)
- 9** Any writeable directory of choice to use to store temporary files.
- 10** If your driver is installed in a non-default namespace, change this value.
- 11** Makes AWS CLI output everything directly to stdout.

b. Create the working directory by running the following command:

```
mkdir -p $SCRATCH_DIR
```

c. Verify cluster connectivity by running the following command in the OpenShift Dedicated CLI:

```
$ oc whoami
```

d. Determine the OpenShift Dedicated cluster type and set node selector:

The EFS cross account feature requires assigning AWS IAM policies to nodes running EFS CSI controller pods. However, this is not consistent for every OpenShift Dedicated type.

- If your cluster is deployed as a Hosted Control Plane (HyperShift), set the **NODE_SELECTOR** environment variable to hold the worker node label by running the following command:

```
export NODE_SELECTOR=node-role.kubernetes.io/worker
```

- For all other OpenShift Dedicated types, set the **NODE_SELECTOR** environment variable to hold the master node label by running the following command:

```
export NODE_SELECTOR=node-role.kubernetes.io/master
```

- e. Configure AWS CLI profiles as environment variables for account switching by running the following commands:

```
export AWS_ACCOUNT_A="<ACCOUNT_A_NAME>"
export AWS_ACCOUNT_B="<ACCOUNT_B_NAME>"
```

- f. Ensure that your AWS CLI is configured with JSON output format as the default for both accounts by running the following commands:

```
export AWS_DEFAULT_PROFILE=${AWS_ACCOUNT_A}
aws configure get output
export AWS_DEFAULT_PROFILE=${AWS_ACCOUNT_B}
aws configure get output
```

If the preceding commands return:

- **No value:** The default output format is already set to JSON and no changes are required.
 - **Any value:** Reconfigure your AWS CLI to use JSON format. For information about changing output formats, see *Setting the output format in the AWS CLI* in the AWS documentation.
- g. Unset **AWS_PROFILE** in your shell to prevent conflicts with **AWS_DEFAULT_PROFILE** by running the following command:

```
unset AWS_PROFILE
```

2. Configure the AWS Account B IAM roles and policies:

- a. Switch to your Account B profile by running the following command:

```
export AWS_DEFAULT_PROFILE=${AWS_ACCOUNT_B}
```

- b. Define the IAM role name for the EFS CSI Driver Operator by running the following command:

```
export ACCOUNT_B_ROLE_NAME=${CLUSTER_NAME}-cross-account-aws-efs-csi-operator
```

- c. Create the IAM trust policy file by running the following command:

```
cat <<EOF > $SCRATCH_DIR/AssumeRolePolicyInAccountB.json
```

```
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Effect": "Allow",
      "Principal": {
        "AWS": "arn:aws:iam::${AWS_ACCOUNT_A_ID}:root"
      },
      "Action": "sts:AssumeRole",
      "Condition": {}
    }
  ]
}
EOF
```

- d. Create the IAM role for the EFS CSI Driver Operator by running the following command:

```
ACCOUNT_B_ROLE_ARN=$(aws iam create-role \
  --role-name "${ACCOUNT_B_ROLE_NAME}" \
  --assume-role-policy-document
file://${SCRATCH_DIR}/AssumeRolePolicyInAccountB.json \
  --query "Role.Arn" --output text) \
&& echo $ACCOUNT_B_ROLE_ARN
```

- e. Create the IAM policy file by running the following command:

```
cat << EOF > ${SCRATCH_DIR}/EfsPolicyInAccountB.json
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Sid": "VisualEditor0",
      "Effect": "Allow",
      "Action": [
        "ec2:DescribeNetworkInterfaces",
        "ec2:DescribeSubnets"
      ],
      "Resource": "*"
    },
    {
      "Sid": "VisualEditor1",
      "Effect": "Allow",
      "Action": [
        "elasticfilesystem:DescribeMountTargets",
        "elasticfilesystem:DeleteAccessPoint",
        "elasticfilesystem:ClientMount",
        "elasticfilesystem:DescribeAccessPoints",
        "elasticfilesystem:ClientWrite",
        "elasticfilesystem:ClientRootAccess",
        "elasticfilesystem:DescribeFileSystems",
        "elasticfilesystem:CreateAccessPoint",
        "elasticfilesystem:TagResource"
      ],
      "Resource": "*"
    }
  ]
}
```

```
}
EOF
```

- f. Create the IAM policy by running the following command:

```
ACCOUNT_B_POLICY_ARN=$(aws iam create-policy --policy-name
"${CLUSTER_NAME}-efs-csi-policy" \
  --policy-document file://$SCRATCH_DIR/EfsPolicyInAccountB.json \
  --query 'Policy.Arn' --output text) \
&& echo ${ACCOUNT_B_POLICY_ARN}
```

- g. Attach the policy to the role by running the following command:

```
aws iam attach-role-policy \
  --role-name "${ACCOUNT_B_ROLE_NAME}" \
  --policy-arn "${ACCOUNT_B_POLICY_ARN}"
```

3. Configure the AWS Account A IAM roles and policies:

- a. Switch to your Account A profile by running the following command:

```
export AWS_DEFAULT_PROFILE=${AWS_ACCOUNT_A}
```

- b. Create the IAM policy document by running the following command:

```
cat << EOF > $SCRATCH_DIR/AssumeRoleInlinePolicyPolicyInAccountA.json
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Effect": "Allow",
      "Action": "sts:AssumeRole",
      "Resource": "${ACCOUNT_B_ROLE_ARN}"
    }
  ]
}
EOF
```

- c. In AWS Account A, attach the AWS-managed policy "AmazonElasticFileSystemClientFullAccess" to the OpenShift Dedicated cluster master role by running the following command:

```
EFS_CLIENT_FULL_ACCESS_BUILTIN_POLICY_ARN=arn:aws:iam::aws:policy/Amazon
ElasticFileSystemClientFullAccess
declare -A ROLE_SEEN
for NODE in $(oc get nodes --selector="${NODE_SELECTOR}" -o
jsonpath='{.items[*].metadata.name}'); do
  INSTANCE_PROFILE=$(aws ec2 describe-instances \
    --filters "Name=private-dns-name,Values=${NODE}" \
    --query 'Reservations[].Instances[].IamInstanceProfile.Arn' \
    --output text | awk -F' ' '{print $NF}' | xargs)
  MASTER_ROLE_ARN=$(aws iam get-instance-profile \
    --instance-profile-name "${INSTANCE_PROFILE}" \
    --query 'InstanceProfile.Roles[0].Arn' \
```

```

--output text | xargs)
MASTER_ROLE_NAME=$(echo "${MASTER_ROLE_ARN}" | awk -F/ '{print $NF}' |
xargs)
echo "Checking role: '${MASTER_ROLE_NAME}'"
if [[ -n "${ROLE_SEEN[${MASTER_ROLE_NAME}:-]}" ]]; then
    echo "Already processed role: '${MASTER_ROLE_NAME}', skipping."
    continue
fi
ROLE_SEEN["${MASTER_ROLE_NAME}"]=1
echo "Assigning policy ${EFS_CLIENT_FULL_ACCESS_BUILTIN_POLICY_ARN} to
role ${MASTER_ROLE_NAME}"
aws iam attach-role-policy --role-name "${MASTER_ROLE_NAME}" --policy-arn
"${EFS_CLIENT_FULL_ACCESS_BUILTIN_POLICY_ARN}"
done

```

4. Attach the policy to the IAM entity to allow role assumption:

This step depends on your cluster configuration. In both of the following scenarios, the EFS CSI Driver Operator uses an entity to authenticate to AWS, and this entity must be granted permission to assume roles in Account B.

If your cluster:

- **Does not have STS enabled** The EFS CSI Driver Operator uses an IAM User entity for AWS authentication. Continue with the step "Attach policy to IAM User to allow role assumption".
- **Has STS enabled:** The EFS CSI Driver Operator uses an IAM role entity for AWS authentication. Continue with the step "Attach policy to IAM Role to allow role assumption".

5. Attach policy to IAM User to allow role assumption

- a. Identify the IAM User used by the EFS CSI Driver Operator by running the following command:

```

EFS_CSI_DRIVER_OPERATOR_USER=$(oc -n openshift-cloud-credential-operator get
credentialsrequest/openshift-aws-efs-csi-driver -o json | jq -r '.status.providerStatus.user')

```

- b. Attach the policy to the IAM user by running the following command:

```

aws iam put-user-policy \
--user-name "${EFS_CSI_DRIVER_OPERATOR_USER}" \
--policy-name efs-cross-account-inline-policy \
--policy-document
file://${SCRATCH_DIR}/AssumeRoleInlinePolicyPolicyInAccountA.json

```

6. Attach the policy to the IAM role to allow role assumption:

- a. Identify the IAM role name currently used by the EFS CSI Driver Operator by running the following command:

```

EFS_CSI_DRIVER_OPERATOR_ROLE=$(oc -n ${CSI_DRIVER_NAMESPACE} get
secret/aws-efs-cloud-credentials -o jsonpath='{.data.credentials}' | base64 -d | grep
role_arn | cut -d/ -f2) && echo ${EFS_CSI_DRIVER_OPERATOR_ROLE}

```

- b. Attach the policy to the IAM role used by the EFS CSI Driver Operator by running the following command:

-

```
aws iam put-role-policy \
  --role-name "${EFS_CSI_DRIVER_OPERATOR_ROLE}" \
  --policy-name efs-cross-account-inline-policy \
  --policy-document
file://$SCRATCH_DIR/AssumeRoleInlinePolicyPolicyInAccountA.json
```

7. Configure VPC peering:

- a. Initiate a peering request from Account A to Account B by running the following command:

```
export AWS_DEFAULT_PROFILE=${AWS_ACCOUNT_A}
PEER_REQUEST_ID=$(aws ec2 create-vpc-peering-connection --vpc-id
"${AWS_ACCOUNT_A_VPC_ID}" --peer-vpc-id "${AWS_ACCOUNT_B_VPC_ID}" --
peer-owner-id "${AWS_ACCOUNT_B_ID}" --query
VpcPeeringConnection.VpcPeeringConnectionId --output text)
```

- b. Accept the peering request from Account B by running the following command:

```
export AWS_DEFAULT_PROFILE=${AWS_ACCOUNT_B}
aws ec2 accept-vpc-peering-connection --vpc-peering-connection-id
"${PEER_REQUEST_ID}"
```

- c. Retrieve the route table IDs for Account A and add routes to the Account B VPC by running the following command:

```
export AWS_DEFAULT_PROFILE=${AWS_ACCOUNT_A}
for NODE in $(oc get nodes --selector=node-role.kubernetes.io/worker | tail -n +2 | awk
'{print $1}')
do
  SUBNET=$(aws ec2 describe-instances --filters "Name=private-dns-
name,Values=$NODE" --query
'Reservations[*].Instances[*].NetworkInterfaces[*].SubnetId' | jq -r '.[0][0][0]')
  echo SUBNET is ${SUBNET}
  ROUTE_TABLE_ID=$(aws ec2 describe-route-tables --filters
"Name=association.subnet-id,Values=${SUBNET}" --query
'RouteTables[*].RouteTableId' | jq -r '.[0]')
  echo Route table ID is $ROUTE_TABLE_ID
  aws ec2 create-route --route-table-id ${ROUTE_TABLE_ID} --destination-cidr-block
${AWS_ACCOUNT_B_VPC_CIDR} --vpc-peering-connection-id
${PEER_REQUEST_ID}
done
```

- d. Retrieve the route table IDs for Account B and add routes to the Account A VPC by running the following command:

```
export AWS_DEFAULT_PROFILE=${AWS_ACCOUNT_B}
for ROUTE_TABLE_ID in $(aws ec2 describe-route-tables --filters "Name=vpc-
id,Values=${AWS_ACCOUNT_B_VPC_ID}" --query "RouteTables[].RouteTableId" | jq -
r '.[0]')
do
  echo Route table ID is $ROUTE_TABLE_ID
  aws ec2 create-route --route-table-id ${ROUTE_TABLE_ID} --destination-cidr-block
${AWS_ACCOUNT_A_VPC_CIDR} --vpc-peering-connection-id
${PEER_REQUEST_ID}
done
```

8. Configure security groups in Account B to allow NFS traffic from Account A to EFS:

- a. Switch to your Account B profile by running the following command:

```
export AWS_DEFAULT_PROFILE=${AWS_ACCOUNT_B}
```

- b. Configure the VPC security groups for EFS access by running the following command:

```
SECURITY_GROUP_ID=$(aws ec2 describe-security-groups --filters Name=vpc-id,Values="${AWS_ACCOUNT_B_VPC_ID}" | jq -r '.SecurityGroups[].GroupId')
aws ec2 authorize-security-group-ingress \
  --group-id "${SECURITY_GROUP_ID}" \
  --protocol tcp \
  --port 2049 \
  --cidr "${AWS_ACCOUNT_A_VPC_CIDR}" | jq .
```

9. Create a region-wide EFS filesystem in Account B:

- a. Switch to your Account B profile by running the following command:

```
export AWS_DEFAULT_PROFILE=${AWS_ACCOUNT_B}
```

- b. Create a region-wide EFS file system by running the following command:

```
CROSS_ACCOUNT_FS_ID=$(aws efs create-file-system --creation-token efs-token-1 \
  --region ${AWS_REGION} \
  --encrypted | jq -r '.FileSystemId') \
&& echo $CROSS_ACCOUNT_FS_ID
```

- c. Configure region-wide mount targets for EFS by running the following command:

```
for SUBNET in $(aws ec2 describe-subnets \
  --filters "Name=vpc-id,Values=${AWS_ACCOUNT_B_VPC_ID}" \
  --region ${AWS_REGION} \
  | jq -r '.Subnets[].SubnetId'); do \
  MOUNT_TARGET=$(aws efs create-mount-target --file-system-id \
    ${CROSS_ACCOUNT_FS_ID} \
    --subnet-id ${SUBNET} \
    --region ${AWS_REGION} \
    | jq -r '.MountTargetId'); \
  echo ${MOUNT_TARGET}; \
done
```

This creates a mount point in each subnet of your VPC.

10. Configure the EFS Operator for cross-account access:

- a. Define custom names for the secret and storage class that you will create in subsequent steps by running the following command:

```
export SECRET_NAME=my-efs-cross-account
export STORAGE_CLASS_NAME=efs-sc-cross
```

- b. Create a secret that references the role ARN in Account B by running the following command in the OpenShift Dedicated CLI:

```
oc create secret generic ${SECRET_NAME} -n ${CSI_DRIVER_NAMESPACE} --from-literal=awsRoleArn="${ACCOUNT_B_ROLE_ARN}"
```

- c. Grant the CSI driver controller access to the newly created secret by running the following commands in the OpenShift Dedicated CLI:

```
oc -n ${CSI_DRIVER_NAMESPACE} create role access-secrets --verb=get,list,watch --resource=secrets
oc -n ${CSI_DRIVER_NAMESPACE} create rolebinding --role=access-secrets default-to-secrets --serviceaccount=${CSI_DRIVER_NAMESPACE}:aws-efs-csi-driver-controller-sa
```

- d. Create a new storage class that references the EFS ID from Account B and the secret created previously by running the following command in the OpenShift Dedicated CLI:


```
cat << EOF | oc apply -f -
kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: ${STORAGE_CLASS_NAME}
provisioner: efs.csi.aws.com
parameters:
  provisioningMode: efs-ap
  filesystemId: ${CROSS_ACCOUNT_FS_ID}
  directoryPerms: "700"
  gidRangeStart: "1000"
  gidRangeEnd: "2000"
  basePath: "/dynamic_provisioning"
  csi.storage.k8s.io/provisioner-secret-name: ${SECRET_NAME}
  csi.storage.k8s.io/provisioner-secret-namespace: ${CSI_DRIVER_NAMESPACE}
EOF
```

Additional resources

- [Setting the output format in the AWS CLI](#)

5.4.6. Dynamic provisioning for Amazon Elastic File Storage

The [AWS EFS CSI driver](#) supports a different form of dynamic provisioning than other CSI drivers. It provisions new PVs as subdirectories of a pre-existing EFS volume. The PVs are independent of each other. However, they all share the same EFS volume. When the volume is deleted, all PVs provisioned out of it are deleted too. The EFS CSI driver creates an AWS Access Point for each such subdirectory. Due to AWS AccessPoint limits, you can only dynamically provision 1000 PVs from a single **StorageClass**/EFS volume.



IMPORTANT

Note that **PVC.spec.resources** is not enforced by EFS.

In the example below, you request 5 GiB of space. However, the created PV is limitless and can store any amount of data (like petabytes). A broken application, or even a rogue application, can cause significant expenses when it stores too much data on the volume.

Using monitoring of EFS volume sizes in AWS is strongly recommended.

Prerequisites

- You have created Amazon Elastic File Storage (Amazon EFS) volumes.
- You have created the AWS EFS storage class.

Procedure

To enable dynamic provisioning:

- Create a PVC (or StatefulSet or Template) as usual, referring to the **StorageClass** created previously.

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: test
spec:
  storageClassName: efs-sc
  accessModes:
    - ReadWriteMany
resources:
  requests:
    storage: 5Gi
```

If you have problems setting up dynamic provisioning, see [AWS EFS troubleshooting](#).

Additional resources

- [Creating the AWS EFS storage class](#)

5.4.7. Creating static PVs with Amazon Elastic File Storage

It is possible to use an Amazon Elastic File Storage (Amazon EFS) volume as a single PV without any dynamic provisioning. The whole volume is mounted to pods.

Prerequisites

- You have created Amazon EFS volumes.

Procedure

- Create the PV using the following YAML file:

```
apiVersion: v1
```

```

kind: PersistentVolume
metadata:
  name: efs-pv
spec:
  capacity: 1
  storage: 5Gi
  volumeMode: Filesystem
  accessModes:
    - ReadWriteMany
    - ReadWriteOnce
  persistentVolumeReclaimPolicy: Retain
  csi:
    driver: efs.csi.aws.com
    volumeHandle: fs-ae66151a 2
    volumeAttributes:
      encryptInTransit: "false" 3

```

- 1 **spec.capacity** does not have any meaning and is ignored by the CSI driver. It is used only when binding to a PVC. Applications can store any amount of data to the volume.
- 2 **volumeHandle** must be the same ID as the EFS volume you created in AWS. If you are providing your own access point, **volumeHandle** should be **<EFS volume ID>::<access point ID>**. For example: **fs-6e633ada::fsap-081a1d293f0004630**.
- 3 If desired, you can disable encryption in transit. Encryption is enabled by default.

If you have problems setting up static PVs, see [AWS EFS troubleshooting](#).

5.4.8. Amazon Elastic File Storage security

The following information is important for Amazon Elastic File Storage (Amazon EFS) security.

When using access points, for example, by using dynamic provisioning as described earlier, Amazon automatically replaces GIDs on files with the GID of the access point. In addition, EFS considers the user ID, group ID, and secondary group IDs of the access point when evaluating file system permissions. EFS ignores the NFS client's IDs. For more information about access points, see <https://docs.aws.amazon.com/efs/latest/ug/efs-access-points.html>.

As a consequence, EFS volumes silently ignore FSGroup; OpenShift Dedicated is not able to replace the GIDs of files on the volume with FSGroup. Any pod that can access a mounted EFS access point can access any file on it.

Unrelated to this, encryption in transit is enabled by default. For more information, see <https://docs.aws.amazon.com/efs/latest/ug/encryption-in-transit.html>.

5.4.9. AWS EFS storage CSI usage metrics

5.4.9.1. Usage metrics overview

Amazon Web Services (AWS) Elastic File Service (EFS) storage Container Storage Interface (CSI) usage metrics allow you to monitor how much space is used by either dynamically or statically provisioned EFS volumes.



IMPORTANT

This feature is disabled by default, because turning on metrics can lead to performance degradation.

The AWS EFS usage metrics feature collects volume metrics in the AWS EFS CSI Driver by recursively walking through the files in the volume. Because this effort can degrade performance, administrators must explicitly enable this feature.

5.4.9.2. Enabling usage metrics using the web console

To enable Amazon Web Services (AWS) Elastic File Service (EFS) Storage Container Storage Interface (CSI) usage metrics using the web console:

1. Click **Administration** > **CustomResourceDefinitions**.
2. On the **CustomResourceDefinitions** page next to the **Name** dropdown box, type **clustercsidriver**.
3. Click **CRD ClusterCSIDriver**.
4. Click the **YAML** tab.
5. Under **spec.aws.efsVolumeMetrics.state**, set the value to **RecursiveWalk**. **RecursiveWalk** indicates that volume metrics collection in the AWS EFS CSI Driver is performed by recursively walking through the files in the volume.

Example ClusterCSIDriver efs.csi.aws.com YAML file

```
spec:
  driverConfig:
    driverType: AWS
    aws:
      efsVolumeMetrics:
        state: RecursiveWalk
        recursiveWalk:
          refreshPeriodMinutes: 100
          fsRateLimit: 10
```

6. Optional: To define how the recursive walk operates, you can also set the following fields:
 - **refreshPeriodMinutes**: Specifies the refresh frequency for volume metrics in minutes. If this field is left blank, a reasonable default is chosen, which is subject to change over time. The current default is 240 minutes. The valid range is 1 to 43,200 minutes.
 - **fsRateLimit**: Defines the rate limit for processing volume metrics in goroutines per file system. If this field is left blank, a reasonable default is chosen, which is subject to change over time. The current default is 5 goroutines. The valid range is 1 to 100 goroutines.
7. Click **Save**.



NOTE

To **disable** AWS EFS CSI usage metrics, use the preceding procedure, but for **spec.aws.efsVolumeMetrics.state**, change the value from **RecursiveWalk** to **Disabled**.

5.4.9.3. Enabling usage metrics using the CLI

To enable Amazon Web Services (AWS) Elastic File Service (EFS) storage Container Storage Interface (CSI) usage metrics using the CLI:

1. Edit ClusterCSIDriver by running the following command:

```
$ oc edit clustercsidriver efs.csi.aws.com
```

2. Under **spec.aws.efsVolumeMetrics.state**, set the value to **RecursiveWalk**. **RecursiveWalk** indicates that volume metrics collection in the AWS EFS CSI Driver is performed by recursively walking through the files in the volume.

Example ClusterCSIDriver efs.csi.aws.com YAML file

```
spec:
  driverConfig:
    driverType: AWS
    aws:
      efsVolumeMetrics:
        state: RecursiveWalk
        recursiveWalk:
          refreshPeriodMinutes: 100
          fsRateLimit: 10
```

3. Optional: To define how the recursive walk operates, you can also set the following fields:
 - **refreshPeriodMinutes**: Specifies the refresh frequency for volume metrics in minutes. If this field is left blank, a reasonable default is chosen, which is subject to change over time. The current default is 240 minutes. The valid range is 1 to 43,200 minutes.
 - **fsRateLimit**: Defines the rate limit for processing volume metrics in goroutines per file system. If this field is left blank, a reasonable default is chosen, which is subject to change over time. The current default is 5 goroutines. The valid range is 1 to 100 goroutines.
4. Save the changes to the **efs.csi.aws.com** object.



NOTE

To **disable** AWS EFS CSI usage metrics, use the preceding procedure, but for **spec.aws.efsVolumeMetrics.state**, change the value from **RecursiveWalk** to **Disabled**.

5.4.10. Amazon Elastic File Storage troubleshooting

The following information provides guidance on how to troubleshoot issues with Amazon Elastic File Storage (Amazon EFS):

- The AWS EFS Operator and CSI driver run in namespace **openshift-cluster-csi-drivers**.
- To initiate gathering of logs of the AWS EFS Operator and CSI driver, run the following command:

```
$ oc adm must-gather
[must-gather ] OUT Using must-gather plugin-in image: quay.io/openshift-release-dev/ocp-v4.0-art-
```

```
dev@sha256:125f183d13601537ff15b3239df95d47f0a604da2847b561151fedd699f5e3a5
[must-gather ] OUT namespace/openshift-must-gather-xm4wq created
[must-gather ] OUT clusterrolebinding.rbac.authorization.k8s.io/must-gather-2bd8x
created
[must-gather ] OUT pod for plug-in image quay.io/openshift-release-dev/ocp-v4.0-art-
dev@sha256:125f183d13601537ff15b3239df95d47f0a604da2847b561151fedd699f5e3a5
created
```

- To show AWS EFS Operator errors, view the **ClusterCSIDriver** status:

```
$ oc get clustercsidriver efs.csi.aws.com -o yaml
```

- If a volume cannot be mounted to a pod (as shown in the output of the following command):

```
$ oc describe pod
...
Type      Reason      Age   From          Message
----      -
Normal    Scheduled   2m13s default-scheduler Successfully assigned default/efs-app to
ip-10-0-135-94.ec2.internal
Warning   FailedMount 13s   kubelet       MountVolume.SetUp failed for volume "pvc-
d7c097e6-67ec-4fae-b968-7e7056796449" : rpc error: code = DeadlineExceeded desc =
context deadline exceeded 1
Warning   FailedMount 10s   kubelet       Unable to attach or mount volumes: unmounted
volumes=[persistent-storage], unattached volumes=[persistent-storage kube-api-access-
9j477]: timed out waiting for the condition
```

- 1** Warning message indicating volume not mounted.

This error is frequently caused by AWS dropping packets between an OpenShift Dedicated node and Amazon EFS.

Check that the following are correct:

- AWS firewall and Security Groups
- Networking: port number and IP addresses

5.4.11. Uninstalling the AWS EFS CSI Driver Operator

All EFS PVs are inaccessible after uninstalling the [AWS EFS CSI Driver Operator](#) (a Red Hat operator).

Prerequisites

- Access to the OpenShift Dedicated web console.

Procedure

To uninstall the AWS EFS CSI Driver Operator from the web console:

1. Log in to the web console.
2. Stop all applications that use AWS EFS PVs.

3. Delete all AWS EFS PVs:
 - a. Click **Storage** → **PersistentVolumeClaims**.
 - b. Select each PVC that is in use by the AWS EFS CSI Driver Operator, click the drop-down menu on the far right of the PVC, and then click **Delete PersistentVolumeClaims**.
4. Uninstall the [AWS EFS CSI driver](#):

**NOTE**

Before you can uninstall the Operator, you must remove the CSI driver first.

- a. Click **Administration** → **CustomResourceDefinitions** → **ClusterCSIDriver**.
 - b. On the **Instances** tab, for **efs.csi.aws.com**, on the far left side, click the drop-down menu, and then click **Delete ClusterCSIDriver**.
 - c. When prompted, click **Delete**.
5. Uninstall the AWS EFS CSI Operator:
 - a. Click **Operators** → **Installed Operators**.
 - b. On the **Installed Operators** page, scroll or type AWS EFS CSI into the **Search by name** box to find the Operator, and then click it.
 - c. On the upper, right of the **Installed Operators > Operator details** page, click **Actions** → **Uninstall Operator**.
 - d. When prompted on the **Uninstall Operator** window, click the **Uninstall** button to remove the Operator from the namespace. Any applications deployed by the Operator on the cluster need to be cleaned up manually.
After uninstalling, the AWS EFS CSI Driver Operator is no longer listed in the **Installed Operators** section of the web console.

**NOTE**

Before you can destroy a cluster (**openshift-install destroy cluster**), you must delete the EFS volume in AWS. An OpenShift Dedicated cluster cannot be destroyed when there is an EFS volume that uses the cluster's VPC. Amazon does not allow deletion of such a VPC.

5.4.12. Additional resources

- [Configuring CSI volumes](#)

5.5. GCP PD CSI DRIVER OPERATOR

5.5.1. Overview

OpenShift Dedicated can provision persistent volumes (PVs) using the Container Storage Interface (CSI) driver for Google Cloud Platform (GCP) persistent disk (PD) storage.

Familiarity with [persistent storage](#) and [configuring CSI volumes](#) is recommended when working with a Container Storage Interface (CSI) Operator and driver.

To create CSI-provisioned persistent volumes (PVs) that mount to GCP PD storage assets, OpenShift Dedicated installs the GCP PD CSI Driver Operator and the GCP PD CSI driver by default in the **openshift-cluster-csi-drivers** namespace.

- **GCP PD CSI Driver Operator:** By default, the Operator provides a storage class that you can use to create PVCs. You can disable this default storage class if desired (see [Managing the default storage class](#)). You also have the option to create the GCP PD storage class as described in [Persistent storage using GCE Persistent Disk](#).
- **GCP PD driver:** The driver enables you to create and mount GCP PD PVs. GCP PD CSI driver supports the C3 instance type for bare metal and N4 machine series. The C3 instance type and N4 machine series support the hyperdisk-balanced disks.

5.5.2. C3 instance type for bare metal and N4 machine series

5.5.2.1. C3 and N4 instance type limitations

The GCP PD CSI driver support for the C3 instance type for bare metal and N4 machine series have the following limitations:

- You must set the volume size to at least 4Gi when you create hyperdisk-balanced disks. OpenShift Dedicated does not round up to the minimum size, so you must specify the correct size yourself.
- Cloning volumes is not supported when using storage pools.
- For cloning or resizing, hyperdisk-balanced disks original volume size must be 6Gi or greater.
- The default storage class is standard-csi.



IMPORTANT

You need to manually create a storage class.

For information about creating the storage class, see Step 2 in Section *Setting up hyperdisk-balanced disks*.

5.5.2.2. Storage pools for hyperdisk-balanced disks overview

Hyperdisk storage pools can be used with Compute Engine for large-scale storage. A hyperdisk storage pool is a purchased collection of capacity, throughput, and IOPS, which you can then provision for your applications as needed. You can use hyperdisk storage pools to create and manage disks in pools and use the disks across multiple workloads. By managing disks in aggregate, you can save costs while achieving expected capacity and performance growth. By using only the storage that you need in hyperdisk storage pools, you reduce the complexity of forecasting capacity and reduce management by going from managing hundreds of disks to managing a single storage pool.

To set up storage pools, see [Setting up hyperdisk-balanced disks](#).

5.5.2.3. Setting up hyperdisk-balanced disks

Prerequisites

- Access to the cluster with administrative privileges

Procedure


Complete the following steps to set up hyperdisk-balanced disks:

1. Create an OpenShift Dedicated cluster on Google Cloud Platform (GCP) with attached disks provisioned with hyperdisk-balanced disks. This can be achieved by provisioning the cluster with compute node types that support hyperdisk-balanced disks, such as the C3 and N4 machine series from Google Cloud Platform (GCP).
2. Once the OSD cluster is ready, navigate to the **OpenShift console** for Storage Class creation. Within the console, navigate to the **Storage** section to create a Storage Class specifying the hyperdisk-balanced disk:

Example StorageClass YAML file

```
kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: hyperdisk-sc 1
  annotations:
    storageclass.kubernetes.io/is-default-class: 'true'
provisioner: pd.csi.storage.gke.io 2
parameters:
  replication-type: none
  storage-pools: projects/myproject/zones/us-east1-c/storagePools/hyperdisk-storagepool 3
  type: hyperdisk-balanced 4
  reclaimPolicy: Delete
  allowVolumeExpansion: true
  volumeBindingMode: Immediate
```

- 1** Specify the name for your storage class. In this example, the name is **hyperdisk-sc**.
- 2** Specify the GCP CSI provisioner as **pd.csi.storage.gke.io**.
- 3** If using storage pools, specify a list of specific storage pools that you want to use in the following format:
projects/PROJECT_ID/zones/ZONE/storagePools/STORAGE_POOL_NAME.
- 4** Specify the disk type as **hyperdisk-balanced**.



NOTE

If you use storage pools, you must first create a Hyperdisk Storage Pool of the type "Hyperdisk Balanced" in the Google Cloud console prior to referencing it in the OpenShift Storage Class. The Hyperdisk Storage Pool must be created in the same zone as the compute node supporting Hyperdisk is installed in the cluster configuration. For more information about creating a Hyperdisk Storage Pool, see [Create a Hyperdisk Storage Pool](#) in the Google Cloud documentation.

3. Create a persistent volume claim (PVC) that uses the hyperdisk-specific storage class using the following example YAML file:

Example PVC YAML file

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: my-pvc
spec:
  storageClassName: hyperdisk-sc 1
  accessModes:
    - ReadWriteOnce
  resources:
    requests:
      storage: 2048Gi 2
```

1 PVC references the storage pool-specific storage class. In this example, **hyperdisk-sc**.

2 Target storage capacity of the hyperdisk-balanced volume. In this example, **2048Gi**.

4. Create a deployment that uses the PVC that you just created. Using a deployment helps ensure that your application has access to the persistent storage even after the pod restarts and rescheduling:
 - a. Ensure a node pool with the specified machine series is up and running before creating the deployment. Otherwise, the pod fails to schedule.
 - b. Use the following example YAML file to create the deployment:

Example deployment YAML file

```
apiVersion: apps/v1
kind: Deployment
metadata:
  name: postgres
spec:
  selector:
    matchLabels:
      app: postgres
  template:
    metadata:
      labels:
        app: postgres
    spec:
      nodeSelector:
        cloud.google.com/machine-family: n4 1
      containers:
        - name: postgres
          image: postgres:14-alpine
          args: [ "sleep", "3600" ]
          volumeMounts:
            - name: sdk-volume
              mountPath: /usr/share/data/
      volumes:
```

```
- name: sdk-volume
  persistentVolumeClaim:
    claimName: my-pvc 2
```

- 1** Specifies the machine family. In this example, it is **n4**.
- 2** Specifies the name of the PVC created in the preceding step. In this example, it is **my-pvc**.

- c. Confirm that the deployment was successfully created by running the following command:

```
$ oc get deployment
```

Example output

```
NAME      READY  UP-TO-DATE  AVAILABLE  AGE
postgres  0/1    1           0          42s
```

It might take a few minutes for hyperdisk instances to complete provisioning and display a READY status.

- d. Confirm that PVC **my-pvc** has been successfully bound to a persistent volume (PV) by running the following command:

```
$ oc get pvc my-pvc
```

Example output

```
NAME      STATUS  VOLUME                                     CAPACITY  ACCESS MODES
STORAGECLASS  VOLUMEATTRIBUTESCLASS  AGE
my-pvc      Bound   pvc-1ff52479-4c81-4481-aa1d-b21c8f8860c6  2Ti       RWO
hyperdisk-sc  <unset>                2m24s
```

- e. Confirm the expected configuration of your hyperdisk-balanced disk:

```
$ gcloud compute disks list
```

Example output

```
NAME                                LOCATION    LOCATION_SCOPE  SIZE_GB  TYPE
STATUS
instance-20240914-173145-boot        us-central1-a zone        150      pd-standard
READY
instance-20240914-173145-data-workspace us-central1-a zone        100      pd-
balanced  READY
c4a-rhel-vm                          us-central1-a zone        50       hyperdisk-balanced
READY 1
```

- 1** Hyperdisk-balanced disk.

- f. If using storage pools, check that the volume is provisioned as specified in your storage class and PVC by running the following command:

```
$ gcloud compute storage-pools list-disks pool-us-east4-c --zone=us-east4-c
```

Example output

```
NAME                                STATUS PROVISIONED_IOPS
PROVISIONED_THROUGHPUT SIZE_GB
pvc-1ff52479-4c81-4481-aa1d-b21c8f8860c6 READY 3000      140
2048
```

5.5.3. About CSI

Storage vendors have traditionally provided storage drivers as part of Kubernetes. With the implementation of the Container Storage Interface (CSI), third-party providers can instead deliver storage plugins using a standard interface without ever having to change the core Kubernetes code.

CSI Operators give OpenShift Dedicated users storage options, such as volume snapshots, that are not possible with in-tree volume plugins.

5.5.4. GCP PD CSI driver storage class parameters

The Google Cloud Platform (GCP) persistent disk (PD) Container Storage Interface (CSI) driver uses the CSI **external-provisioner** sidecar as a controller. This is a separate helper container that is deployed with the CSI driver. The sidecar manages persistent volumes (PVs) by triggering the **CreateVolume** operation.

The GCP PD CSI driver uses the **csi.storage.k8s.io/fstype** parameter key to support dynamic provisioning. The following table describes all the GCP PD CSI storage class parameters that are supported by OpenShift Dedicated.

Table 5.2. CreateVolume Parameters

Parameter	Values	Default	Description
type	pd-ssd , pd-standard , or pd-balanced	pd-standard	Allows you to choose between standard PVs or solid-state-drive PVs. The driver does not validate the value, thus all the possible values are accepted.
replication-type	none or regional-pd	none	Allows you to choose between zonal or regional PVs.
disk-encryption-kms-key	Fully qualified resource identifier for the key to use to encrypt new disks.	Empty string	Uses customer-managed encryption keys (CMEK) to encrypt new disks.

5.5.5. Creating a custom-encrypted persistent volume

When you create a **PersistentVolumeClaim** object, OpenShift Dedicated provisions a new persistent volume (PV) and creates a **PersistentVolume** object. You can add a custom encryption key in Google Cloud Platform (GCP) to protect a PV in your cluster by encrypting the newly created PV.

For encryption, the newly attached PV that you create uses customer-managed encryption keys (CMEK) on a cluster by using a new or existing Google Cloud Key Management Service (KMS) key.

Prerequisites

- You are logged in to a running OpenShift Dedicated cluster.
- You have created a Cloud KMS key ring and key version.

For more information about CMEK and Cloud KMS resources, see [Using customer-managed encryption keys \(CMEK\)](#).

Procedure

To create a custom-encrypted PV, complete the following steps:

1. Create a storage class with the Cloud KMS key. The following example enables dynamic provisioning of encrypted volumes:

```
apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
  name: csi-gce-pd-cmek
provisioner: pd.csi.storage.gke.io
volumeBindingMode: "WaitForFirstConsumer"
allowVolumeExpansion: true
parameters:
  type: pd-standard
  disk-encryption-kms-key: projects/<key-project-id>/locations/<location>/keyRings/<key-
ring>/cryptoKeys/<key> 1
```

- 1** This field must be the resource identifier for the key that will be used to encrypt new disks. Values are case-sensitive. For more information about providing key ID values, see [Retrieving a resource's ID](#) and [Getting a Cloud KMS resource ID](#).



NOTE

You cannot add the **disk-encryption-kms-key** parameter to an existing storage class. However, you can delete the storage class and recreate it with the same name and a different set of parameters. If you do this, the provisioner of the existing class must be **pd.csi.storage.gke.io**.

2. Deploy the storage class on your OpenShift Dedicated cluster using the **oc** command:

```
$ oc describe storageclass csi-gce-pd-cmek
```

Example output

```
Name:          csi-gce-pd-cmek
```

```

IsDefaultClass:    No
Annotations:       None
Provisioner:       pd.csi.storage.gke.io
Parameters:        disk-encryption-kms-key=projects/key-project-
id/locations/location/keyRings/ring-name/cryptoKeys/key-name,type=pd-standard
AllowVolumeExpansion: true
MountOptions:      none
ReclaimPolicy:     Delete
VolumeBindingMode: WaitForFirstConsumer
Events:            none

```

3. Create a file named **pvc.yaml** that matches the name of your storage class object that you created in the previous step:

```

kind: PersistentVolumeClaim
apiVersion: v1
metadata:
  name: podpvc
spec:
  accessModes:
    - ReadWriteOnce
  storageClassName: csi-gce-pd-cmek
  resources:
    requests:
      storage: 6Gi

```



NOTE

If you marked the new storage class as default, you can omit the **storageClassName** field.

4. Apply the PVC on your cluster:

```
$ oc apply -f pvc.yaml
```

5. Get the status of your PVC and verify that it is created and bound to a newly provisioned PV:

```
$ oc get pvc
```

Example output

NAME	STATUS	VOLUME	CAPACITY	ACCESS MODES
STORAGECLASS	AGE			
podpvc	Bound	pvc-e36abf50-84f3-11e8-8538-42010a800002	10Gi	RWO
csi-gce-pd-cmek	9s			



NOTE

If your storage class has the **volumeBindingMode** field set to **WaitForFirstConsumer**, you must create a pod to use the PVC before you can verify it.

Your CMEK-protected PV is now ready to use with your OpenShift Dedicated cluster.

5.5.6. Additional resources

- [Persistent storage using GCE Persistent Disk](#)
- [Configuring CSI volumes](#)

5.6. GOOGLE COMPUTE PLATFORM FILESTORE CSI DRIVER OPERATOR

5.6.1. Overview

OpenShift Dedicated is capable of provisioning persistent volumes (PVs) using the Container Storage Interface (CSI) driver for Google Compute Platform (GCP) Filestore Storage.

Familiarity with [persistent storage](#) and [configuring CSI volumes](#) is recommended when working with a CSI Operator and driver.

To create CSI-provisioned PVs that mount to Google Cloud Filestore Storage assets, you install the Google Cloud Filestore CSI Driver Operator and the Google Cloud Filestore CSI driver in the **openshift-cluster-csi-drivers** namespace.

- The *Google Cloud Filestore CSI Driver Operator* does not provide a storage class by default, but [you can create one if needed](#). The Google Cloud Filestore CSI Driver Operator supports dynamic volume provisioning by allowing storage volumes to be created on demand, eliminating the need for cluster administrators to pre-provision storage.
- The *Google Cloud Filestore CSI driver* enables you to create and mount Google Cloud Filestore PVs.

OpenShift Dedicated Google Cloud Filestore supports Workload Identity. This allows users to access Google Cloud resources using federated identities instead of a service account key. GCP Workload Identity must be enabled globally during installation, and then configured for the Google Cloud Filestore CSI Driver Operator. For more information, see [Installing the Google Cloud Filestore CSI Driver Operator](#).

5.6.2. About CSI

Storage vendors have traditionally provided storage drivers as part of Kubernetes. With the implementation of the Container Storage Interface (CSI), third-party providers can instead deliver storage plugins using a standard interface without ever having to change the core Kubernetes code.

CSI Operators give OpenShift Dedicated users storage options, such as volume snapshots, that are not possible with in-tree volume plugins.

5.6.3. Installing the Google Cloud Filestore CSI Driver Operator

5.6.3.1. Preparing to install the Google Cloud Filestore CSI Driver Operator with Workload Identity

If you are planning to use GCP Workload Identity with Google Compute Platform Filestore, you must obtain certain parameters that you will use during the installation of the Google Cloud Filestore Container Storage Interface (CSI) Driver Operator.

Prerequisites

- Access to the cluster as a user with the cluster-admin role.

Procedure

To prepare to install the Google Cloud Filestore CSI Driver Operator with Workload Identity:

1. Obtain the project number:

- a. Obtain the project ID by running the following command:

```
$ export PROJECT_ID=$(oc get infrastructure/cluster -o
jsonpath='{.status.platformStatus.gcp.projectID}')
```

- b. Obtain the project number, using the project ID, by running the following command:

```
$ gcloud projects describe $PROJECT_ID --format="value(projectNumber)"
```

2. Find the identity pool ID and the provider ID:

During cluster installation, the names of these resources are provided to the Cloud Credential Operator utility (**ccctl**) with the **--name parameter**. See "Creating Google Cloud resources with the Cloud Credential Operator utility".

3. Create Workload Identity resources for the Google Cloud Filestore Operator:

- a. Create a **CredentialsRequest** file using the following example file:

Example Credentials Request YAML file

```
apiVersion: cloudcredential.openshift.io/v1
kind: CredentialsRequest
metadata:
  name: openshift-gcp-filestore-csi-driver-operator
  namespace: openshift-cloud-credential-operator
  annotations:
    include.release.openshift.io/self-managed-high-availability: "true"
    include.release.openshift.io/single-node-developer: "true"
spec:
  serviceAccountNames:
    - gcp-filestore-csi-driver-operator
    - gcp-filestore-csi-driver-controller-sa
  secretRef:
    name: gcp-filestore-cloud-credentials
    namespace: openshift-cluster-csi-drivers
  providerSpec:
    apiVersion: cloudcredential.openshift.io/v1
    kind: GCPProviderSpec
    predefinedRoles:
      - roles/file.editor
      - roles/resourcemanager.tagUser
    skipServiceCheck: true
```

- b. Use the **CredentialsRequest** file to create a Google Cloud service account by running the following command:

```
$ ./ccctl gcp create-service-accounts --name=<filestore-service-account> \ ❶
--workload-identity-pool=<workload-identity-pool> \ ❷
--workload-identity-provider=<workload-identity-provider> \ ❸
--project=<project-id> \ ❹
--credentials-requests-dir=/tmp/credreq ❺
```

- ❶ <filestore-service-account> is a user-chosen name.
- ❷ <workload-identity-pool> comes from Step 2 above.
- ❸ <workload-identity-provider> comes from Step 2 above.
- ❹ <project-id> comes from Step 1.a above.
- ❺ The name of directory where the **CredentialsRequest** file resides.

Example output

```
2025/02/10 17:47:39 Credentials loaded from gcloud CLI defaults
2025/02/10 17:47:42 IAM service account filestore-service-account-openshift-gcp-
filestore-csi-driver-operator created
2025/02/10 17:47:44 Unable to add predefined roles to IAM service account, retrying...
2025/02/10 17:47:59 Updated policy bindings for IAM service account filestore-service-
account-openshift-gcp-filestore-csi-driver-operator
2025/02/10 17:47:59 Saved credentials configuration to: /tmp/install-dir/ ❶
openshift-cluster-csi-drivers-gcp-filestore-cloud-credentials-credentials.yaml
```

- ❶ The current directory.

- c. Find the service account email of the newly created service account by running the following command:

```
$ cat /tmp/install-dir/manifests/openshift-cluster-csi-drivers-gcp-filestore-cloud-
credentials-credentials.yaml | yq '.data["service_account.json"]' | base64 -d | jq
'.service_account_impersonation_url'
```

Example output

```
https://iamcredentials.googleapis.com/v1/projects/-/serviceAccounts/filestore-se-
openshift-g-ch8cm@openshift-gce-
devel.iam.gserviceaccount.com:generateAccessToken
```

In this example output, the service account email is **filestore-se-openshift-g-ch8cm@openshift-gce-devel.iam.gserviceaccount.com**.

Results

You now have the following parameters that you need to install the Google Cloud Filestore CSI Driver Operator:

- Project number - from Step 1.b
- Pool ID - from Step 2
- Provider ID - from Step 2
- Service account email - from Step 3.c

5.6.3.2. Installing the Google Cloud Filestore CSI Driver Operator

The Google Compute Platform (Google Cloud) Filestore Container Storage Interface (CSI) Driver Operator is not installed in OpenShift Dedicated by default. Use the following procedure to install the Google Cloud Filestore CSI Driver Operator in your cluster.

Prerequisites

- Access to the OpenShift Dedicated web console.
- If using GCP Workload Identity, certain GCP Workload Identity parameters are needed. See the preceding Section *Preparing to install the Google Cloud Filestore CSI Driver Operator with Workload Identity*.

Procedure

To install the Google Cloud Filestore CSI Driver Operator from the web console:

1. Log in to the [OpenShift Cluster Manager](#).
2. Select your cluster.
3. Click **Open console** and log in with your credentials.
4. Enable the Filestore API in the GCE project by running the following command:

```
$ gcloud services enable file.googleapis.com --project <my_gce_project> 1
```

- 1** Replace **<my_gce_project>** with your Google Cloud project.

You can also do this using Google Cloud web console.

5. Install the Google Cloud Filestore CSI Operator:
 - a. Click **Operators** → **OperatorHub**.
 - b. Locate the Google Cloud Filestore CSI Operator by typing **Google Cloud Filestore** in the filter box.
 - c. Click the **Google Cloud Filestore CSI Driver Operator** button.
 - d. On the **Google Cloud Filestore CSI Driver Operator** page, click **Install**.
 - e. On the **Install Operator** page, ensure that:

- **All namespaces on the cluster (default)** is selected.
 - **Installed Namespace** is set to **openshift-cluster-csi-drivers**.
If using GCP Workload Identity, enter values for the following fields obtained from the procedure in Section *Preparing to install the Google Cloud Filestore CSI Driver Operator with Workload Identity*.
 - **Google Cloud Project Number**
 - **Google Cloud Pool ID**
 - **Google Cloud Provider ID**
 - **Google Cloud Service Account Email**
- f. Click **Install**.
After the installation finishes, the Google Cloud Filestore CSI Operator is listed in the **Installed Operators** section of the web console.
6. Install the Google Cloud Filestore CSI Driver:
- a. Click **administration** → **CustomResourceDefinitions** → **ClusterCSIDriver**.
 - b. On the **Instances** tab, click **Create ClusterCSIDriver**.
Use the following YAML file:


```
apiVersion: operator.openshift.io/v1
kind: ClusterCSIDriver
metadata:
  name: filestore.csi.storage.gke.io
spec:
  managementState: Managed
```
 - c. Click **Create**.
 - d. Wait for the following Conditions to change to a "true" status:
 - GCPFilestoreDriverCredentialsRequestControllerAvailable
 - GCPFilestoreDriverNodeServiceControllerAvailable
 - GCPFilestoreDriverControllerServiceControllerAvailable

Additional resources

- [Enabling an API in your Google Cloud](#) .
- [Enabling an API using the Google Cloud web console](#) .

5.6.4. Creating a storage class for GCP Filestore Storage

After installing the Operator, you should create a storage class for dynamic provisioning of Google Compute Platform (GCP) Filestore volumes.

Prerequisites

- You are logged in to the running OpenShift Dedicated cluster.

Procedure

To create a storage class:

1. Create a storage class using the following example YAML file:

Example YAML file

```
kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: filestore-csi
provisioner: filestore.csi.storage.gke.io
parameters:
  connect-mode: DIRECT_PEERING 1
  network: network-name 2
allowVolumeExpansion: true
volumeBindingMode: WaitForFirstConsumer
```

- 1** For a shared VPC, use the **connect-mode** parameter set to **PRIVATE_SERVICE_ACCESS**. For a non-shared VPC, the value is **DIRECT_PEERING**, which is the default setting.
- 2** Specify the name of the GCP virtual private cloud (VPC) network where Filestore instances should be created in.

2. Specify the name of the VPC network where Filestore instances should be created in.
It is recommended to specify the VPC network that the Filestore instances should be created in. If no VPC network is specified, the Container Storage Interface (CSI) driver tries to create the instances in the default VPC network of the project.

On IPI installations, the VPC network name is typically the cluster name with the suffix "-network". However, on UPI installations, the VPC network name can be any value chosen by the user.

For a shared VPC (**connect-mode** = **PRIVATE_SERVICE_ACCESS**), the network needs to be the full VPC name. For example: **projects/shared-vpc-name/global/networks/gcp-filestore-network**.

You can find out the VPC network name by inspecting the **MachineSets** objects with the following command:

```
$ oc -n openshift-machine-api get machinesets -o yaml | grep "network:"
- network: gcp-filestore-network
(...)
```

In this example, the VPC network name in this cluster is "gcp-filestore-network".

5.6.5. NFS export options

By default, a Filestore instance grants root level read/write access to all clients that share the same Google Cloud project and virtual private cloud (VPC) network. Network File System (NFS) export

options can limit this access to certain IP ranges and specific user/group IDs for the Filestore instance. When creating a storage class, you can set these options using the **nfs-export-options-on-create** parameter.

Prerequisites

- Access to the cluster as a user with the cluster-admin role.
- The Google Cloud Filestore CSI Driver Operator and Google Cloud Filestore CSI driver installed.

Procedure

1. Create a storage class using a file similar to the following sample YAML file:



NOTE

For more information about creating a storage class, see Section *Creating a storage class for GCP Filestore Operator*.

Example storage class YAML file with NFS export options

```
kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: SC-name
provisioner: filestore.csi.storage.gke.io
parameters:
  connect-mode: DIRECT_PEERING
  network: project-network
  nfs-export-options-on-create: '[ 1
  {
    "accessMode": "READ_WRITE", 2
    "squashMode": "NO_ROOT_SQUASH", 3
    "anonUid": 65534 4
    "anonGid": 65534 5
    "ipRanges": [ 6
      "10.0.0.0/16"
    ]
  }
]'
allowVolumeExpansion: true
```

1 NFS export options parameter

2 Access mode: Either **READ_ONLY**, which allows only read requests on the exported directory; or **READ_WRITE**, which allows both read and write requests. The default is **READ_WRITE**.

3 Squash mode: Either **NO_ROOT_SQUASH**, which allows root access on the exported directory; or **ROOT_SQUASH**, which does not allow root access. The default is **NO_ROOT_SQUASH**.

4

AnonUid: An integer representing the anonymous user ID with a default value of 65534.

AnonUid can only be set with **squashMode** set to **ROOT_SQUASH**; Otherwise, an error

- 5 **AnonGid:** An integer representing the anonymous group ID with a default value of 65534. **AnonGid** can only be set with **squashMode** set to **ROOT_SQUASH**. Otherwise, an error occurs.

- 6 **IP ranges:** List of either an IPv4 addresses in the format {octet1}.{octet2}.{octet3}.{octet4}, or CIDR ranges in the format {octet1}.{octet2}.{octet3}.{octet4}/{mask size}, which can mount the file share. Overlapping IP ranges are not allowed, both within and across NfsExportOptions, otherwise, an error is returned. The limit is 64 IP ranges or addresses for each **FileShareConfig** among all NFS export options.

5.6.6. Destroying clusters and GCP Filestore

Typically, if you destroy a cluster, the OpenShift Dedicated installer deletes all of the cloud resources that belong to that cluster. However, due to the special nature of the Google Compute Platform (GCP) Filestore resources, the automated cleanup process might not remove all of them in some rare cases.

Therefore, Red Hat recommends that you verify that all cluster-owned Filestore resources are deleted by the uninstall process.

Procedure

To ensure that all GCP Filestore PVCs have been deleted:

1. Access your Google Cloud account using the GUI or CLI.
2. Search for any resources with the **kubernetes-io-cluster-`{CLUSTER_ID}`=owned** label. Since the cluster ID is unique to the deleted cluster, there should not be any remaining resources with that cluster ID.
3. In the unlikely case there are some remaining resources, delete them.

5.6.7. Additional resources

- [Configuring CSI volumes](#)

CHAPTER 6. GENERIC EPHEMERAL VOLUMES

6.1. OVERVIEW

Generic ephemeral volumes are a type of ephemeral volume that can be provided by all storage drivers that support persistent volumes and dynamic provisioning. Generic ephemeral volumes are similar to **emptyDir** volumes in that they provide a per-pod directory for scratch data, which is usually empty after provisioning.

Generic ephemeral volumes are specified inline in the pod spec and follow the pod's lifecycle. They are created and deleted along with the pod.

Generic ephemeral volumes have the following features:

- Storage can be local or network-attached.
- Volumes can have a fixed size that pods are not able to exceed.
- Volumes might have some initial data, depending on the driver and parameters.
- Typical operations on volumes are supported, assuming that the driver supports them, including snapshotting, cloning, resizing, and storage capacity tracking.



NOTE

Generic ephemeral volumes do not support offline snapshots and resize.

6.2. LIFECYCLE AND PERSISTENT VOLUME CLAIMS

The parameters for a volume claim are allowed inside a volume source of a pod. Labels, annotations, and the whole set of fields for persistent volume claims (PVCs) are supported. When such a pod is created, the ephemeral volume controller then creates an actual PVC object (from the template shown in the *Creating generic ephemeral volumes* procedure) in the same namespace as the pod, and ensures that the PVC is deleted when the pod is deleted. This triggers volume binding and provisioning in one of two ways:

- Either immediately, if the storage class uses immediate volume binding. With immediate binding, the scheduler is forced to select a node that has access to the volume after it is available.
- When the pod is tentatively scheduled onto a node (**WaitForFirstConsumervolume** binding mode). This volume binding option is recommended for generic ephemeral volumes because then the scheduler can choose a suitable node for the pod.

In terms of resource ownership, a pod that has generic ephemeral storage is the owner of the PVCs that provide that ephemeral storage. When the pod is deleted, the Kubernetes garbage collector deletes the PVC, which then usually triggers deletion of the volume because the default reclaim policy of storage classes is to delete volumes. You can create quasi-ephemeral local storage by using a storage class with a reclaim policy of retain: the storage outlives the pod, and in this case, you must ensure that volume clean-up happens separately. While these PVCs exist, they can be used like any other PVC. In particular, they can be referenced as data sources in volume cloning or snapshotting. The PVC object also holds the current status of the volume.

Additional resources

- [Creating generic ephemeral volumes](#)

6.3. SECURITY

You can enable the generic ephemeral volume feature to allow users who can create pods to also create persistent volume claims (PVCs) indirectly. This feature works even if these users do not have permission to create PVCs directly. Cluster administrators must be aware of this. If this does not fit your security model, use an admission webhook that rejects objects such as pods that have a generic ephemeral volume.


The normal namespace quota for PVCs still applies, so even if users are allowed to use this new mechanism, they cannot use it to circumvent other policies.

6.4. PERSISTENT VOLUME CLAIM NAMING

Automatically created persistent volume claims (PVCs) are named by a combination of the pod name and the volume name, with a hyphen (-) in the middle. This naming convention also introduces a potential conflict between different pods, and between pods and manually created PVCs.

For example, **pod-a** with volume **scratch** and **pod** with volume **a-scratch** both end up with the same PVC name, **pod-a-scratch**.

Such conflicts are detected, and a PVC is only used for an ephemeral volume if it was created for the pod. This check is based on the ownership relationship. An existing PVC is not overwritten or modified, but this does not resolve the conflict. Without the right PVC, a pod cannot start.



IMPORTANT

Be careful when naming pods and volumes inside the same namespace so that naming conflicts do not occur.

6.5. CREATING GENERIC EPHEMERAL VOLUMES

Procedure

1. Create the **pod** object definition and save it to a file.
2. Include the generic ephemeral volume information in the file.

my-example-pod-with-generic-vols.yaml

```
kind: Pod
apiVersion: v1
metadata:
  name: my-app
spec:
  containers:
  - name: my-frontend
    image: busybox:1.28
    volumeMounts:
    - mountPath: "/mnt/storage"
      name: data
```

```
    command: [ "sleep", "1000000" ]  
volumes:  
  - name: data 1  
    ephemeral:  
      volumeClaimTemplate:  
        metadata:  
          labels:  
            type: my-app-ephvol  
        spec:  
          accessModes: [ "ReadWriteOnce" ]  
          storageClassName: "gp2-csi"  
          resources:  
            requests:  
              storage: 1Gi
```

1 Generic ephemeral volume claim.

CHAPTER 7. EXPANDING PERSISTENT VOLUMES

7.1. ENABLING VOLUME EXPANSION SUPPORT

Before you can expand persistent volumes, the **StorageClass** object must have the **allowVolumeExpansion** field set to **true**.

Procedure

- Edit the **StorageClass** object and add the **allowVolumeExpansion** attribute by running the following command:

```
$ oc edit storageclass <storage_class_name> 1
```

- 1 Specifies the name of the storage class.

The following example demonstrates adding this line at the bottom of the storage class configuration.

```
apiVersion: storage.k8s.io/v1
kind: StorageClass
...
parameters:
  type: gp2
  reclaimPolicy: Delete
  allowVolumeExpansion: true 1
```

- 1 Setting this attribute to **true** allows PVCs to be expanded after creation.

7.2. EXPANDING CSI VOLUMES

You can use the Container Storage Interface (CSI) to expand storage volumes after they have already been created.

Shrinking persistent volumes (PVs) is *not* supported.

Prerequisites

- The underlying CSI driver supports `resize`. See "CSI drivers supported by OpenShift Dedicated" in the "Additional resources" section.
- Dynamic provisioning is used.
- The controlling **StorageClass** object has **allowVolumeExpansion** set to **true**. For more information, see "Enabling volume expansion support."

Procedure

1. For the persistent volume claim (PVC), set **.spec.resources.requests.storage** to the desired new size.

2. Watch the **status.conditions** field of the PVC to see if the resize has completed. OpenShift Dedicated adds the **Resizing** condition to the PVC during expansion, which is removed after expansion completes.

7.3. EXPANDING LOCAL VOLUMES

You can manually expand persistent volumes (PVs) and persistent volume claims (PVCs) created by using the local storage operator (LSO).

Procedure

1. Expand the underlying devices. Ensure that appropriate capacity is available on these devices.
2. Update the corresponding PV objects to match the new device sizes by editing the **.spec.capacity** field of the PV.
3. For the storage class that is used for binding the PVC to PVet, set **allowVolumeExpansion:true**.
4. For the PVC, set **.spec.resources.requests.storage** to match the new size.

Kubelet should automatically expand the underlying file system on the volume, if necessary, and update the status field of the PVC to reflect the new size.

7.4. EXPANDING PERSISTENT VOLUME CLAIMS (PVCS) WITH A FILE SYSTEM

Expanding PVCs based on volume types that need file system resizing, such as GCE, EBS, and Cinder, is a two-step process. First, expand the volume objects in the cloud provider. Second, expand the file system on the node.

Expanding the file system on the node only happens when a new pod is started with the volume.

Prerequisites

- The controlling **StorageClass** object must have **allowVolumeExpansion** set to **true**.

Procedure

1. Edit the PVC and request a new size by editing **spec.resources.requests**. For example, the following expands the **ebs** PVC to 8 Gi:

```
kind: PersistentVolumeClaim
apiVersion: v1
metadata:
  name: ebs
spec:
  storageClass: "storageClassWithFlagSet"
  accessModes:
    - ReadWriteOnce
  resources:
    requests:
      storage: 8Gi 1
```

- 1 Updating **spec.resources.requests** to a larger amount expands the PVC.
2. After the cloud provider object has finished resizing, the PVC is set to **FileSystemResizePending**. Check the condition by entering the following command:

```
$ oc describe pvc <pvc_name>
```

3. When the cloud provider object has finished resizing, the **PersistentVolume** object reflects the newly requested size in **PersistentVolume.Spec.Capacity**. At this point, you can create or recreate a new pod from the PVC to finish the file system resizing. Once the pod is running, the newly requested size is available and the **FileSystemResizePending** condition is removed from the PVC.

7.5. RECOVERING FROM FAILURE WHEN EXPANDING VOLUMES

If a resize request fails or remains in a pending state, you can try again by entering a different resize value in **.spec.resources.requests.storage** for the persistent volume claim (PVC). The new value must be larger than the original volume size.

If you are still having issues, use the following procedure to recover.

Procedure

If entering another smaller resize value in **.spec.resources.requests.storage** for the PVC does not work, do the following:

1. Mark the persistent volume (PV) that is bound to the PVC with the **Retain** reclaim policy. Change **persistentVolumeReclaimPolicy** to **Retain**.
2. Delete the PVC.
3. Manually edit the PV and delete the **claimRef** entry from the PV specs to ensure that the newly created PVC can bind to the PV marked **Retain**. This marks the PV as **Available**.
4. Re-create the PVC in a smaller size, or a size that can be allocated by the underlying storage provider.
5. Set the **volumeName** field of the PVC to the name of the PV. This binds the PVC to the provisioned PV only.
6. Restore the reclaim policy on the PV.

7.6. ADDITIONAL RESOURCES

- [Enabling volume expansion support](#)
- [CSI drivers supported by OpenShift Dedicated](#)

CHAPTER 8. DYNAMIC PROVISIONING

8.1. ABOUT DYNAMIC PROVISIONING

The **StorageClass** resource object describes and classifies storage that can be requested, as well as provides a means for passing parameters for dynamically provisioned storage on demand.

StorageClass objects can also serve as a management mechanism for controlling different levels of storage and access to the storage. Cluster Administrators (**cluster-admin**) or Storage Administrators (**storage-admin**) define and create the **StorageClass** objects that users can request without needing any detailed knowledge about the underlying storage volume sources.


The OpenShift Dedicated persistent volume framework enables this functionality and allows administrators to provision a cluster with persistent storage. The framework also gives users a way to request those resources without having any knowledge of the underlying infrastructure.

Many storage types are available for use as persistent volumes in OpenShift Dedicated. While all of them can be statically provisioned by an administrator, some types of storage are created dynamically using the built-in provider and plugin APIs.

8.2. AVAILABLE DYNAMIC PROVISIONING PLUGINS

OpenShift Dedicated provides the following provisioner plugins, which have generic implementations for dynamic provisioning that use the cluster's configured provider's API to create new storage resources:


Storage type	Provisioner plugin name	Notes
Amazon Elastic Block Store (Amazon EBS)	ebs.csi.aws.com	For dynamic provisioning when using multiple clusters in different zones, tag each node with Key=kubernetes.io/cluster/<cluster_name>,Value=<cluster_id> where <cluster_name> and <cluster_id> are unique per cluster.
GCE Persistent Disk (gcePD)	kubernetes.io/gce-pd	In multi-zone configurations, it is advisable to run one OpenShift Dedicated cluster per GCE project to avoid PVs from being created in zones where no node in the current cluster exists.
IBM Power® Virtual Server Block	powervs.csi.ibm.com	After installation, the IBM Power® Virtual Server Block CSI Driver Operator and IBM Power® Virtual Server Block CSI Driver automatically create the required storage classes for dynamic provisioning.

**IMPORTANT**

Any chosen provisioner plugin also requires configuration for the relevant cloud, host, or third-party provider as per the relevant documentation.

8.3. DEFINING A STORAGE CLASS

StorageClass objects are currently a globally scoped object and must be created by **cluster-admin** or **storage-admin** users.

**IMPORTANT**

The Cluster Storage Operator might install a default storage class depending on the platform in use. This storage class is owned and controlled by the Operator. It cannot be deleted or modified beyond defining annotations and labels. If different behavior is desired, you must define a custom storage class.

The following sections describe the basic definition for a **StorageClass** object and specific examples for each of the supported plugin types.

8.3.1. Basic StorageClass object definition

The following resource shows the parameters and default values that you use to configure a storage class. This example uses the AWS ElasticBlockStore (EBS) object definition.

Sample StorageClass definition

```
kind: StorageClass ❶
apiVersion: storage.k8s.io/v1 ❷
metadata:
  name: <storage-class-name> ❸
  annotations: ❹
    storageclass.kubernetes.io/is-default-class: 'true'
  ...
provisioner: kubernetes.io/aws-ebs ❺
parameters: ❻
  type: gp3
...
```

- ❶ (required) The API object type.
- ❷ (required) The current apiVersion.
- ❸ (required) The name of the storage class.
- ❹ (optional) Annotations for the storage class.
- ❺ (required) The type of provisioner associated with this storage class.
- ❻ (optional) The parameters required for the specific provisioner, this will change from plug-in to plug-in.

8.3.2. Storage class annotations

To set a storage class as the cluster-wide default, add the following annotation to your storage class metadata:

```
storageclass.kubernetes.io/is-default-class: "true"
```

For example:

```
apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
  annotations:
    storageclass.kubernetes.io/is-default-class: "true"
...
```

This enables any persistent volume claim (PVC) that does not specify a specific storage class to automatically be provisioned through the default storage class. However, your cluster can have more than one storage class, but only one of them can be the default storage class.



NOTE

The beta annotation **storageclass.beta.kubernetes.io/is-default-class** is still working; however, it will be removed in a future release.

To set a storage class description, add the following annotation to your storage class metadata:

```
kubernetes.io/description: My Storage Class Description
```

For example:

```
apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
  annotations:
    kubernetes.io/description: My Storage Class Description
...
```

8.3.3. AWS Elastic Block Store (EBS) object definition

aws-ebs-storageclass.yaml

```
kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: <storage-class-name> 1
provisioner: ebs.csi.aws.com
parameters:
  type: io1 2
  iopsPerGB: "10" 3
```

```
encrypted: "true" 4
kmsKeyId: keyvalue 5
fsType: ext4 6
```

- 1 (required) Name of the storage class. The persistent volume claim uses this storage class for provisioning the associated persistent volumes.
- 2 (required) Select from **io1**, **gp3**, **sc1**, **st1**. The default is **gp3**. See the [AWS documentation](#) for valid Amazon Resource Name (ARN) values.
- 3 Optional: Only for **io1** volumes. I/O operations per second per GiB. The AWS volume plugin multiplies this with the size of the requested volume to compute IOPS of the volume. The value cap is 20,000 IOPS, which is the maximum supported by AWS. See the [AWS documentation](#) for further details.
- 4 Optional: Denotes whether to encrypt the EBS volume. Valid values are **true** or **false**.
- 5 Optional: The full ARN of the key to use when encrypting the volume. If none is supplied, but **encrypted** is set to **true**, then AWS generates a key. See the [AWS documentation](#) for a valid ARN value.
- 6 Optional: File system that is created on dynamically provisioned volumes. This value is copied to the **fsType** field of dynamically provisioned persistent volumes and the file system is created when the volume is mounted for the first time. The default value is **ext4**.

8.3.4. GCE PersistentDisk (gcePD) object definition

gce-pd-storageclass.yaml

```
apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
  name: <storage-class-name> 1
provisioner: kubernetes.io/gce-pd
parameters:
  type: pd-ssd 2
  replication-type: none
volumeBindingMode: WaitForFirstConsumer
allowVolumeExpansion: true
reclaimPolicy: Delete
```

- 1 Name of the storage class. The persistent volume claim uses this storage class for provisioning the associated persistent volumes.
- 2 Select **pd-ssd**, **pd-standard**, or **hyperdisk-balanced**. The default is **pd-ssd**.

8.4. CHANGING THE DEFAULT STORAGE CLASS

Use the following procedure to change the default storage class.

For example, if you have two defined storage classes, **gp3** and **standard**, and you want to change the default storage class from **gp3** to **standard**.

Prerequisites

- Access to the cluster with cluster-admin privileges.

Procedure

To change the default storage class:

1. List the storage classes:

```
$ oc get storageclass
```

Example output

NAME	TYPE
gp3 (default)	ebs.csi.aws.com 1
standard	ebs.csi.aws.com

- 1** **(default)** indicates the default storage class.

2. Make the desired storage class the default.

For the desired storage class, set the **storageclass.kubernetes.io/is-default-class** annotation to **true** by running the following command:

```
$ oc patch storageclass standard -p '{"metadata": {"annotations": {"storageclass.kubernetes.io/is-default-class": "true"}}}'
```



NOTE

You can have multiple default storage classes for a short time. However, you should ensure that only one default storage class exists eventually.

With multiple default storage classes present, any persistent volume claim (PVC) requesting the default storage class (**pvc.spec.storageClassName=nil**) gets the most recently created default storage class, regardless of the default status of that storage class, and the administrator receives an alert in the alerts dashboard that there are multiple default storage classes, **MultipleDefaultStorageClasses**.

3. Remove the default storage class setting from the old default storage class.

For the old default storage class, change the value of the **storageclass.kubernetes.io/is-default-class** annotation to **false** by running the following command:

```
$ oc patch storageclass gp3 -p '{"metadata": {"annotations": {"storageclass.kubernetes.io/is-default-class": "false"}}}'
```

4. Verify the changes:

```
$ oc get storageclass
```

Example output

NAME	TYPE
------	------

	gp3	ebs.csi.aws.com
	standard (default)	ebs.csi.aws.com