



Red Hat Ceph Storage 3

Ceph File System Guide

Configuring and Mounting Ceph File Systems

Red Hat Ceph Storage 3 Ceph File System Guide

Configuring and Mounting Ceph File Systems

Legal Notice

Copyright © 2021 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

<http://creativecommons.org/licenses/by-sa/3.0/>

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, the Red Hat logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux[®] is the registered trademark of Linus Torvalds in the United States and other countries.

Java[®] is a registered trademark of Oracle and/or its affiliates.

XFS[®] is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL[®] is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js[®] is an official trademark of Joyent. Red Hat is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack[®] Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

Abstract

This guide describes how to configure the Ceph Metadata Server (MDS) and how to create, mount and work the Ceph File System (CephFS).

Table of Contents

CHAPTER 1. INTRODUCTION TO CEPH FILE SYSTEM	5
1.1. ABOUT THE CEPH FILE SYSTEM	5
The Ceph File System Components	5
1.2. MAIN CEPHFS FEATURES	6
1.3. CEPHFS LIMITATIONS	7
1.4. DIFFERENCES FROM POSIX COMPLIANCE IN THE CEPH FILE SYSTEM	8
1.5. ADDITIONAL RESOURCES	8
CHAPTER 2. CONFIGURING METADATA SERVER DAEMONS	9
2.1. PREREQUISITES	9
2.2. STATES OF METADATA SERVER DAEMONS	9
What Happens When the Active MDS Daemon Fails	10
2.3. EXPLANATION OF RANKS IN METADATA SERVER CONFIGURATION	10
Rank States	10
2.4. TYPES OF STANDBY CONFIGURATION	10
Prerequisites	10
Configuration Parameters	10
Standby Replay	11
Standby for Name	11
Standby for Rank	11
Standby for FSCID	11
2.5. CONFIGURING STANDBY METADATA SERVER DAEMONS	11
Procedure	11
Additional Resources	12
2.6. CONFIGURING MULTIPLE ACTIVE METADATA SERVER DAEMONS	12
Procedure	12
Additional Resources	13
2.7. DECREASING THE NUMBER OF ACTIVE MDS DAEMONS	13
Prerequisites	13
Procedure	14
Additional Resources	15
2.8. UNDERSTANDING MDS CACHE SIZE LIMITS	15
Additional Resources	15
2.9. ADDITIONAL RESOURCES	16
CHAPTER 3. DEPLOYING CEPH FILE SYSTEMS	17
3.1. PREREQUISITES	17
3.2. CREATING THE CEPH FILE SYSTEMS	17
Prerequisites	17
Procedure	18
Additional Resources	19
3.3. CREATING CEPH FILE SYSTEM CLIENT USERS	19
Procedure	19
Additional Resources	21
3.4. MOUNTING THE CEPH FILE SYSTEM AS A KERNEL CLIENT	21
3.4.1. Prerequisites	21
3.4.2. Manually Mounting the Ceph File System as a kernel Client	22
Additional Resources	23
3.4.3. Automatically Mounting the Ceph File System as a kernel Client	23
Prerequisites	23
Procedure	23

3.5. MOUNTING THE CEPH FILE SYSTEM AS A FUSE CLIENT	24
3.5.1. Prerequisites	24
3.5.2. Manually Mounting the Ceph File System as a FUSE Client	25
Prerequisites	25
Procedure	25
Additional Resources	26
3.5.3. Automatically Mounting the Ceph File System as a FUSE Client	26
Prerequisites	26
Procedure	26
3.6. CREATING CEPH FILE SYSTEMS WITH ERASURE CODING	26
CHAPTER 4. ADMINISTERING CEPH FILE SYSTEMS	30
4.1. PREREQUISITES	30
4.2. MAPPING DIRECTORY TREES TO MDS RANKS	30
Prerequisites	30
Procedure	30
Additional Resources	31
4.3. DISASSOCIATING DIRECTORY TREES FROM MDS RANKS	31
Prerequisites	31
Procedure	31
Additional Resources	31
4.4. WORKING WITH FILE AND DIRECTORY LAYOUTS	31
4.4.1. Prerequisites	31
4.4.2. Understanding File and Directory Layouts	31
Layouts Inheritance	32
4.4.3. Setting File and Directory Layouts	32
Procedure	33
Additional Resources	33
4.4.4. Viewing File and Directory Layouts	33
Procedure	33
Additional Resources	34
4.4.5. Removing Directory Layouts	34
Procedure	34
Additional Resources	35
4.5. ADDING DATA POOLS	35
Procedure	35
4.6. WORKING WITH CEPH FILE SYSTEM QUOTAS	36
4.6.1. Prerequisites	36
4.6.2. Ceph File System quotas	36
4.6.3. Viewing quotas	37
4.6.4. Setting quotas	37
4.6.5. Removing quotas	38
4.6.6. Additional Resources	39
4.7. REMOVING CEPH FILE SYSTEMS	39
CHAPTER 5. UNMOUNTING CEPH FILE SYSTEMS	42
5.1. UNMOUNTING CEPH FILE SYSTEMS MOUNTED AS KERNEL CLIENTS	42
Procedure	42
Additional Resources	42
5.2. UNMOUNTING CEPH FILE SYSTEMS MOUNTED AS FUSE CLIENTS	42
Procedure	42
Additional Resources	42
APPENDIX A. TROUBLESHOOTING	43

A.1. CEPHFS HEALTH MESSAGES	43
APPENDIX B. CONFIGURATION REFERENCE	45
B.1. MDS CONFIGURATION REFERENCE	45
B.2. JOURNALER CONFIGURATION REFERENCE	59
B.3. FUSE CLIENT CONFIGURATION REFERENCE	61
Developer Options	66

CHAPTER 1. INTRODUCTION TO CEPH FILE SYSTEM

This chapter explains what the Ceph File System (CephFS) is and how it works.

1.1. ABOUT THE CEPH FILE SYSTEM


The Ceph File System (CephFS) is a file system compatible with POSIX standards that provides a file access to a Ceph Storage Cluster.

The CephFS requires at least one Metadata Server (MDS) daemon (**ceph-mds**) to run. The MDS daemon manages metadata related to files stored on the Ceph File System and also coordinates access to the shared Ceph Storage Cluster.

CephFS uses the POSIX semantics wherever possible. For example, in contrast to many other common network file systems like NFS, CephFS maintains strong cache coherency across clients. The goal is for processes using the file system to behave the same when they are on different hosts as when they are on the same host. However, in some cases, CephFS diverges from the strict POSIX semantics. For details, see [Section 1.4, "Differences from POSIX Compliance in the Ceph File System"](#) .

The Ceph File System Components

This picture shows various layers of the Ceph File System.



The bottom layer represents the underlying core cluster that includes:


- OSDs (**ceph-osd**) where the Ceph File System data and metadata are stored
- Metadata Servers (**ceph-mds**) that manages Ceph File System metadata
- Monitors (**ceph-mon**) that manages the master copy of the cluster map

The Ceph Storage Cluster Protocol layer represents the Ceph native **librados** library for interacting with the core cluster.

The CephFS library layer includes the CephFS **libcephfs** library that works on top of **librados** and represents the Ceph File System.

The upper layer represents two types of clients that can access the Ceph File Systems.

This picture shows in more detail how the Ceph File System components interact with each other.



The Ceph File System has the following primary components:

- *Clients* represent the entities performing I/O operations on behalf of applications using CephFS (**ceph-fuse** for FUSE clients and **kcephfs** for kernel clients). Clients send metadata requests to active MDS. In return, the client learns of file metadata and can begin safely caching both metadata and file data.
- *Metadata Servers* serves metadata to clients, caches hot metadata to reduce requests to the backing metadata pool store, manages client caches to maintain cache coherency, replicates hot metadata between active MDS, and coalesces metadata mutations to a compact journal with regular flushes to the backing metadata pool.

1.2. MAIN CEPHFS FEATURES

The Ceph File System introduces the following features and enhancements:

Scalability

The Ceph File System is highly scalable due to horizontal scaling of metadata servers and direct client reads and writes with individual OSD nodes.

Shared File System

The Ceph File System is a shared file system so multiple clients can work on the same file system at once.

High Availability

The Ceph File System provides a cluster of Ceph Metadata Servers (MDS). One is active and others are in standby mode. If the active MDS terminates unexpectedly, one of the standby MDS becomes active. As a result, client mounts continue working through a server failure. This behavior makes the Ceph File System highly available. In addition, you can configure multiple active metadata servers. See [Section 2.6, "Configuring Multiple Active Metadata Server Daemons"](#) for details.

Configurable File and Directory Layouts

The Ceph File System allows users to configure file and directory layouts to use multiple pools, pool namespaces, and file striping modes across objects. See [Section 4.4, “Working with File and Directory Layouts”](#) for details.

POSIX Access Control Lists (ACL)

The Ceph File System supports the POSIX Access Control Lists (ACL). ACL are enabled by default with the Ceph File Systems mounted as kernel clients with kernel version **kernel-3.10.0-327.18.2.el7**. To use ACL with the Ceph File Systems mounted as FUSE clients, you must enable them. See [Section 1.3, “CephFS Limitations”](#) for details.

Client Quotas

The Ceph File System FUSE client supports setting quotas on any directory in a system. The quota can restrict the number of bytes or the number of files stored beneath that point in the directory hierarchy. Client quotas are enabled by default.

1.3. CEPHFS LIMITATIONS

Access Control Lists (ACL) support in FUSE clients

To use the ACL feature with the Ceph File System mounted as a FUSE client, you must enable it. To do so, add the following options to the Ceph configuration file:

```
[client]
client_acl_type=posix_acl
```

Then restart the Ceph client.

Snapshots

Creating snapshots is not enabled by default because this feature is still experimental and it can cause the MDS or client nodes to terminate unexpectedly.

If you understand the risks and still wish to enable snapshots, use:

```
ceph mds set allow_new_snaps true --yes-i-really-mean-it
```

Multiple Ceph File Systems

By default, creation of multiple Ceph File Systems in one cluster is disabled. An attempt to create an additional Ceph File System fails with the following error:

```
Error EINVAL: Creation of multiple filesystems is disabled.
```

Creating multiple Ceph File Systems in one cluster is not fully supported yet and can cause the MDS or client nodes to terminate unexpectedly.

If you understand the risks and still wish to enable multiple Ceph file systems, use:

```
ceph fs flag set enable_multiple true --yes-i-really-mean-it
```

1.4. DIFFERENCES FROM POSIX COMPLIANCE IN THE CEPH FILE SYSTEM

This section lists situations where the Ceph File System (CephFS) diverges from the strict POSIX semantics.

- If a client's attempt to write a file fails, the write operations are not necessarily atomic. That is, the client might call the **write()** system call on a file opened with the **O_SYNC** flag with an 8MB buffer and then terminates unexpectedly and the write operation can be only partially applied. Almost all file systems, even local file systems, have this behavior.
- In situations when the write operations occur simultaneously, a write operation that exceeds object boundaries is not necessarily atomic. For example, writer A writes "**aa|aa**" and writer B writes "**bb|bb**" simultaneously (where "|" is the object boundary) and "**aa|bb**" is written rather than the proper "**aa|aa**" or "**bb|bb**".
- POSIX includes the **telldir()** and **seekdir()** system calls that allow you to obtain the current directory offset and seek back to it. Because CephFS can fragment directories at any time, it is difficult to return a stable integer offset for a directory. As such, calling the **seekdir()** system call to a non-zero offset might often work but is not guaranteed to do so. Calling **seekdir()** to offset 0 will always work. This is an equivalent to the **rewinddir()** system call.
- Sparse files propagate incorrectly to the **st_blocks** field of the **stat()** system call. Because CephFS does not explicitly track which parts of a file are allocated or written, the **st_blocks** field is always populated by the file size divided by the block size. This behavior causes utilities, such as **du**, to overestimate consumed space.
- When the **mmap()** system call maps a file into memory on multiple hosts, write operations are not coherently propagated to caches of other hosts. That is, if a page is cached on host A, and then updated on host B, host A page is not coherently invalidated.
- CephFS clients present a hidden **.snap** directory that is used to access, create, delete, and rename snapshots. Although this directory is excluded from the **readdir()** system call, any process that tries to create a file or directory with the same name returns an error. You can change the name of this hidden directory at mount time with the **-o snapdirname=**<new_name>**** option or by using the **client_snapdir** configuration option.

1.5. ADDITIONAL RESOURCES

- If you want to use NFS Ganesha as an interface to the Ceph File System with Red Hat OpenStack Platform, see the [CephFS with NFS-Ganesha deployment](#) section in the *CephFS via NFS Back End Guide for the Shared File System Service* for instructions on how to deploy such an environment.

CHAPTER 2. CONFIGURING METADATA SERVER DAEMONS

This chapter explains how to configure Ceph Metadata Server (MDS) daemons.

- To understand different states of MDS daemons, see [Section 2.2, “States of Metadata Server Daemons”](#).
- To understand what a "rank" mean in MDS configuration, see [Section 2.3, “Explanation of Ranks in Metadata Server Configuration”](#).
- To learn about various configuration types of standby MDS daemons, see [Section 2.4, “Types of Standby Configuration”](#).
- To configure standby MDS daemons, see [Section 2.5, “Configuring Standby Metadata Server Daemons”](#).
- To configure multiple active MDS daemons, see [Section 2.6, “Configuring Multiple Active Metadata Server Daemons”](#).
- To decrease the number of active MDS daemons, see [Section 2.7, “Decreasing the Number of Active MDS Daemons”](#).
- To learn about MDS cache size limits, see [Section 2.8, “Understanding MDS Cache Size Limits”](#).



NOTE

Starting with Red Hat Ceph Storage 3.2, the **ceph-mds** and **ceph-fuse** daemons can run with SELinux in enforcing mode.

2.1. PREREQUISITES

- Deploy a Ceph Storage Cluster if you do not have one. For details, see the [Installation Guide for Red Hat Enterprise Linux](#) or [Ubuntu](#).
- Install Ceph Metadata Server daemons (**ceph-mds**). For details, see the [Installation Guide for Red Hat Enterprise Linux](#) or [Ubuntu](#).

2.2. STATES OF METADATA SERVER DAEMONS

This section explains two different modes of Metadata Server (MDS) daemons and how a daemon in one mode starts operating in the other mode.

The MDS daemons can be:

- Active
- Standby

The **active** MDS daemon manages the metadata for files and directories stored on the Ceph File System. The **standby** MDS daemons serves as backup daemons and become active when an active MDS daemon becomes unresponsive.

By default, a Ceph File System uses only one active MDS daemon. However, you can configure the file system to use multiple active MDS daemons to scale metadata performance for larger workloads. The active MDS daemons will share the metadata workload with one another dynamically when metadata

load patterns change. Typically, systems with many clients benefit from multiple active MDS daemons. Note that systems with multiple active MDS daemons still require standby MDS daemons to remain highly available.

What Happens When the Active MDS Daemon Fails

When the active MDS becomes unresponsive, a Monitor will wait the number of seconds specified by the **mds_beacon_grace** option. Then the Monitor marks the MDS daemon as **laggy** and one of the standby daemons becomes active depending on the configuration.

To change the value of **mds_beacon_grace**, add this option to the Ceph configuration file and specify the new value.

2.3. EXPLANATION OF RANKS IN METADATA SERVER CONFIGURATION

Each Ceph File System has a number of ranks, one by default, which starts at zero.

Ranks define the way how the metadata workload is shared between multiple Metadata Server (MDS) daemons. The number of ranks is the maximum number of MDS daemons that can be active at one time. Each MDS daemon handles a subset of the Ceph File System metadata that is assigned to that rank.

Each MDS daemon initially starts without a rank. The Monitor assigns a rank to the daemon. An MDS daemon can only hold one rank at a time. Daemons only lose ranks when they are stopped.

The **max_mds** setting controls how many ranks will be created.

The actual number of ranks in the Ceph File System is only increased if a spare daemon is available to accept the new rank.

Rank States

Ranks can be:

- **Up** - A rank that is assigned to an MDS daemon.
- **Failed** - A rank that is not associated with any MDS daemon.
- **Damaged** - A rank that is damaged; its metadata is corrupted or missing. Damaged ranks will not be assigned to any MDS daemons until the operators fixes the problem and uses the **ceph mds repaired** command on the damaged rank.

2.4. TYPES OF STANDBY CONFIGURATION

This section describes various types of standby daemons configuration.

Prerequisites

- Familiarize yourself with the meaning of *rank* in Ceph File System context. See [Section 2.3, “Explanation of Ranks in Metadata Server Configuration”](#) for details.

Configuration Parameters

By default, all Metadata Server daemons that do not hold a rank are standby daemons for any active daemon. However, you can configure how the MDS daemons behave in standby mode by using the following parameters in the Ceph configuration file.

- **mds_standby_replay** ([Standby Replay](#))

- **mds_standby_for_name** (Standby for Name)
- **mds_standby_for_rank** (Standby for Rank)
- **mds_standby_for_fscid** (Standby for FSCID)

You can set these parameters in the Ceph configuration file on the host where the MDS daemon runs as opposed to the one on the Monitor node. The MDS daemon loads these settings when it starts and sends them to the Monitor node.

Standby Replay

When the **mds_standby_replay** option is set to **true** for a daemon, this daemon will continuously read the metadata journal of a rank associated with another MDS daemon (the **up** rank). This behavior gives the standby replay daemon a more recent metadata cache and makes the failover process faster if the daemon serving the rank fails.

An **up** rank can only have one standby replay daemon assigned to it. If two daemons are both set to be standby replay then one of them becomes a normal non-replay standby daemon.

If the **mon_force_standby_active** option is set to **false**, a standby replay daemon is only used as a standby for the rank that it is following. If another rank fails, the standby replay daemon will not be used as a replacement, even if no other standby daemons are available. By default, **mon_force_standby_active** is set to **true**.

Standby for Name

Each daemon has a static name that is set by the administrator when configuring the daemon for the first time. Usually, the host name of the host where the daemon runs is used as the daemon name.

When setting the **mds_standby_for_name** option, the standby daemon only takes over a failed rank if the name of the daemon that previously held the rank matches the given name.

Standby for Rank

Set the **mds_standby_for_rank** option to configure the standby daemon to only take over the specified rank. If another rank fails, this daemon will not replace it.

If you have multiple file systems, use this option in conjunction with the **mds_standby_for_fscid** option to specify which file system rank you target.

Standby for FSCID

The File System Cluster ID (FSCID) is an integer ID specific to a Ceph File System.

If the **mds_standby_for_fscid** option is used in conjunction with **mds_standby_for_rank** it only specifies which file system rank is referred to.

If **mds_standby_for_rank** is not set, then setting **mds_standby_for_fscid** causes the standby daemon to target any rank in the specified FSCID. Use **mds_standby_for_fscid** if you want to use the standby daemon for any rank, but only within a particular file system.

2.5. CONFIGURING STANDBY METADATA SERVER DAEMONS

This section describes how to configure Metadata Server (MDS) daemons in standby mode to better manage a failure of the active MDS daemon.

Procedure

- Edit the Ceph configuration file. You can edit the main Ceph configuration file present on all nodes, or you can use different configuration files on each MDS node that contain just

configuration related to that node. Use parameters described in [Section 2.4, “Types of Standby Configuration”](#).

- For example, to configure two MDS daemons **a** and **b** acting, as a pair, where whichever one has not currently assigned a rank will be the standby replay follower of the other:

```
[mds.a]
mds_standby_replay = true
mds_standby_for_rank = 0

[mds.b]
mds_standby_replay = true
mds_standby_for_rank = 0
```

- For example, to configure four MDS daemons (**a**, **b**, **c**, and **d**) on two Ceph File Systems, where each File System has a pair of daemons:

```
[mds.a]
mds_standby_for_fscid = 1

[mds.b]
mds_standby_for_fscid = 1

[mds.c]
mds_standby_for_fscid = 2

[mds.d]
mds_standby_for_fscid = 2
```

Additional Resources

- [Section 2.2, “States of Metadata Server Daemons”](#)

2.6. CONFIGURING MULTIPLE ACTIVE METADATA SERVER DAEMONS

This section describes how to configure multiple active Metadata Server (MDS) daemons to scale metadata performance for large systems.



IMPORTANT

Do not convert all standby MDS daemons to active ones. A Ceph File System requires at least one standby MDS daemon to remain highly available.



IMPORTANT

The scrubbing process is not currently supported when multiple active MDS daemons are configured.

Procedure

- On a node with administration capabilities, set the **max_mds** parameter to the desired number of active MDS daemons. Note that Ceph only increases the actual number of ranks in the Ceph File Systems if a spare MDS daemon is available to take the new rank.


```
ceph fs set <name> max_mds <number>
```

For example, to increase the number of active MDS daemons to two in the Ceph File System called **cephfs**:

```
[root@monitor ~]# ceph fs set cephfs max_mds 2
```

2. Verify the number of active MDS daemons.

```
ceph fs status <name>
```

Specify the name of the Ceph File System, for example:

```
[root@monitor ~]# ceph fs status cephfs
cephfs - 0 clients
=====
+-----+-----+-----+-----+-----+-----+
| Rank | State | MDS | Activity | dns | inos |
+-----+-----+-----+-----+-----+
| 0 | active | node1 | Reqs: 0/s | 10 | 12 |
| 1 | active | node2 | Reqs: 0/s | 10 | 12 |
+-----+-----+-----+-----+-----+
+-----+-----+-----+-----+
| Pool | type | used | avail |
+-----+-----+-----+-----+
| cephfs_metadata | metadata | 4638 | 26.7G |
| cephfs_data | data | 0 | 26.7G |
+-----+-----+-----+-----+

+-----+
| Standby MDS |
+-----+
| node3 |
+-----+
```

Additional Resources

- [Section 2.2, “States of Metadata Server Daemons”](#)
- [Section 2.7, “Decreasing the Number of Active MDS Daemons”](#)

2.7. DECREASING THE NUMBER OF ACTIVE MDS DAEMONS

This section describes how to decrease the number of active MDS daemons.

Prerequisites

- The rank that you will remove must be active first, meaning that you must have the same number of MDS daemons as specified by the **max_mds** parameter.

```
ceph fs status <name>
```

Specify the name of the Ceph File System, for example:

```
[root@monitor ~]# ceph fs status cephfs
cephfs - 0 clients
=====
+-----+-----+-----+-----+-----+-----+
| Rank | State | MDS | Activity | dns | inos |
+-----+-----+-----+-----+-----+
| 0 | active | node1 | Reqs: 0/s | 10 | 12 |
| 1 | active | node2 | Reqs: 0/s | 10 | 12 |
+-----+-----+-----+-----+-----+
+-----+-----+-----+-----+
| Pool | type | used | avail |
+-----+-----+-----+-----+
| cephfs_metadata | metadata | 4638 | 26.7G |
| cephfs_data | data | 0 | 26.7G |
+-----+-----+-----+-----+

+-----+
| Standby MDS |
+-----+
| node3 |
+-----+
```

Procedure

1. On a node with administration capabilities, change the **max_mds** parameter to the desired number of active MDS daemons.

```
ceph fs set <name> max_mds <number>
```

For example, to decrease the number of active MDS daemons to one in the Ceph File System called **cephfs**:

```
[root@monitor ~]# ceph fs set cephfs max_mds 1
```

2. Deactivate the active MDS daemon:

```
ceph mds deactivate <role>
```

Replace **<role>** with "name of the Ceph File System:rank", "FSID:rank", or just rank. For example, to deactivate the MDS daemon with rank 1 on the Ceph File System named **cephfs**:

```
[root@monitor ~]# ceph mds deactivate cephfs:1
telling mds.1:1 127.0.0.1:6800/3187061458 to deactivate
```

3. Verify the number of active MDS daemons.

```
ceph fs status <name>
```

Specify the name of the Ceph File System, for example:

```
[root@monitor ~]# ceph fs status cephfs
cephfs - 0 clients
=====
```

```

+-----+-----+-----+-----+-----+-----+
| Rank | State | MDS | Activity | dns | inos |
+-----+-----+-----+-----+-----+-----+
| 0 | active | node1 | Reqs: 0 /s | 10 | 12 |
+-----+-----+-----+-----+-----+
+-----+-----+-----+-----+
| Pool | type | used | avail |
+-----+-----+-----+-----+
| cephfs_metadata | metadata | 4638 | 26.7G |
| cephfs_data | data | 0 | 26.7G |
+-----+-----+-----+-----+

+-----+
| Standby MDS |
+-----+
| node3 |
| node2 |
+-----+

```

Additional Resources

- [Section 2.2, “States of Metadata Server Daemons”](#)
- [Section 2.6, “Configuring Multiple Active Metadata Server Daemons”](#)

2.8. UNDERSTANDING MDS CACHE SIZE LIMITS

This section describes ways to limit MDS cache size.

You can limit the size of the Metadata Server (MDS) cache by:

- **A memory limit** A new behavior introduced in the Red Hat Ceph Storage 3. Use the **mds_cache_memory_limit** parameters. Red Hat recommends to use memory limits instead of inode count limits.
- **Inode count:** Use the **mds_cache_size** parameter. By default, limiting the MDS cache by inode count is disabled.

In addition, you can specify a cache reservation by using the **mds_cache_reservation** parameter for MDS operations. The cache reservation is limited as a percentage of the memory or inode limit and is set to 5% by default. The intent of this parameter is to have the MDS maintain an extra reserve of memory for its cache for new metadata operations to use. As a consequence, the MDS should in general operate below its memory limit because it will recall old state from clients in order to drop unused metadata in its cache.

The **mds_cache_reservation** parameter replaces the **mds_health_cache_threshold** in all situations except when MDS nodes sends a health alert to the Monitors indicating the cache is too large. By default, **mds_health_cache_threshold** is 150% of the maximum cache size.

Be aware that the cache limit is not a hard limit. Potential bugs in the CephFS client or MDS or misbehaving applications might cause the MDS to exceed its cache size. The **mds_health_cache_threshold** configures the cluster health warning message so that operators can investigate why the MDS cannot shrink its cache.

Additional Resources

- [MDS Configuration Reference](#)

2.9. ADDITIONAL RESOURCES

- The [Installation Guide for Red Hat Enterprise Linux](#)
- The [Installation Guide for Ubuntu](#)

CHAPTER 3. DEPLOYING CEPH FILE SYSTEMS

This chapter describes how to create and mount Ceph File Systems.

To deploy a Ceph File System:

1. Create a Ceph file system on a Monitor node. See [Section 3.2, “Creating the Ceph File Systems”](#) for details.
2. Create a client user with the correct access rights and permissions and make its key available on the node where the Ceph File System will be mounted. See [Section 3.3, “Creating Ceph File System Client Users”](#) for details.
3. Mount CephFS on a dedicated node. Choose one of the following methods:
 - a. Mounting CephFS as a kernel client. See [Section 3.4, “Mounting the Ceph File System as a kernel client”](#)
 - b. Mounting CephFS as a FUSE client. See [Section 3.5, “Mounting the Ceph File System as a FUSE Client”](#)

3.1. PREREQUISITES

- Deploy a Ceph Storage Cluster if you do not have one. For details, see the [Installation Guide for Red Hat Enterprise Linux](#) or [Ubuntu](#).
- Install and configure Ceph Metadata Server daemons (**ceph-mds**). For details, see the [Installation Guide for Red Hat Enterprise Linux](#) or [Ubuntu](#) and [Chapter 2, Configuring Metadata Server Daemons](#).

3.2. CREATING THE CEPH FILE SYSTEMS

This section describes how to create a Ceph File System on a Monitor node.



IMPORTANT

By default, you can create only one Ceph File System in the Ceph Storage Cluster. See [Section 1.3, “CephFS Limitations”](#) for details.

Prerequisites

- Deploy a Ceph Storage Cluster if you do not have one. For details, see the [Installation Guide for Red Hat Enterprise Linux](#) or the [Installation Guide for Ubuntu](#).
- Install and configure Ceph Metadata Server daemons (**ceph-mds**). For details, see [Installing Metadata Servers](#) in the [Installation Guide for Red Hat Enterprise Linux](#) or the [Installation Guide for Ubuntu](#).
- Install **ceph-common** package.

- On Red Hat Enterprise Linux:

```
# yum install ceph-common
```

- On Ubuntu:

```
$ sudo apt-get install ceph-common
```



NOTE

To enable the repo and install **ceph-common** package on the defined client nodes, see *Installing the Ceph Client Role* in the [Installation Guide for Red Hat Enterprise Linux](#) or the [Installation Guide for Ubuntu](#).

Procedure

Use the following commands from a Monitor host and as the **root** user.


1. Create two pools, one for storing data and one for storing metadata:

```
ceph osd pool create <name> <pg_num>
```

Specify the pool name and the number of placement groups (PGs), for example:

```
[root@monitor ~]# ceph osd pool create cephfs-data 64
[root@monitor ~]# ceph osd pool create cephfs-metadata 64
```

Typically, the metadata pool can start with a conservative number of PGs as it will generally have far fewer objects than the data pool. It is possible to increase the number of PGs if needed. Recommended metadata pool sizes range from 64 PGs to 512 PGs. Size the data pool proportional to the number and sizes of files you expect in the file system.



IMPORTANT

For the metadata pool, consider using

- A higher replication level because any data loss to this pool can make the whole file system inaccessible
- Storage with lower latency such as Solid-state Drive (SSD) disks because this directly affects the observed latency of file system operations on clients

2. Create the Ceph File System:

```
ceph fs new <name> <metadata-pool> <data-pool>
```

Specify the name of the Ceph File System, the metadata and data pool, for example:

```
[root@monitor ~]# ceph fs new cephfs cephfs-metadata cephfs-data
```

3. Verify that one or more MDSs enter to the active state based on you configuration.

```
ceph fs status <name>
```

Specify the name of the Ceph File System, for example:

```
[root@monitor ~]# ceph fs status cephfs
cephfs - 0 clients
=====
```

```

+-----+-----+-----+-----+-----+-----+
| Rank | State | MDS | Activity | dns | inos |
+-----+-----+-----+-----+-----+-----+
| 0 | active | node1 | Reqs: 0 /s | 10 | 12 |
+-----+-----+-----+-----+-----+
+-----+-----+-----+-----+
| Pool | type | used | avail |
+-----+-----+-----+-----+
| cephfs_metadata | metadata | 4638 | 26.7G |
| cephfs_data | data | 0 | 26.7G |
+-----+-----+-----+-----+

+-----+
| Standby MDS |
+-----+
| node3 |
| node2 |
+-----+

```

Additional Resources

- The [Enabling the Red Hat Ceph Storage Repositories](#) section in Red Hat Ceph Storage 3 *Installation Guide for Red Hat Enterprise Linux*
- The [Enabling the Red Hat Ceph Storage Repositories](#) Red Hat Ceph Storage 3 *Installation Guide for Ubuntu*
- The [Pools](#) chapter in the *Storage Strategies* guide for Red Hat Ceph Storage 3

3.3. CREATING CEPH FILE SYSTEM CLIENT USERS

Red Hat Ceph Storage 3 uses **cephx** for authentication, which is enabled by default. To use **cephx** with Ceph File System, create a user with the correct authorization capabilities on a Monitor node and make its key available on the node where the Ceph File System will be mounted.

To make the key available for use with the kernel client, create a secret file on the client node with the key inside it. To make the key available for the File System in User Space (FUSE) client, copy the keyring to the client node.

Procedure

1. On a Monitor host, create a client user.

```
ceph auth get-or-create client.<id> <capabilities>
```

Specify the client ID and desired capabilities.

- To restrict the client to only write to and read from a particular pool in the cluster:

```
ceph auth get-or-create client.1 mon 'allow r' mds 'allow rw' osd 'allow rw pool=<pool>'
```

For example, to restrict the client to only write to and read from the **data** pool:

```
[root@monitor ~]# ceph auth get-or-create client.1 mon 'allow r' mds 'allow rw' osd 'allow rw pool=data'
```

- To prevent the client from modifying the pool that is used for files and directories:

```
[root@monitor ~]# ceph auth get-or-create client.1 mon 'allow r' mds 'allow r' osd 'allow r
pool=<pool>'
```

For example, to prevent the client from modifying **data** pool:

```
[root@monitor ~]# ceph auth get-or-create client.1 mon 'allow r' mds 'allow r' osd 'allow r
pool=data'
```



NOTE

Do not create capabilities for the **metadata** pool, as Ceph File System clients do not have access to it.

2. Verify the created key:

```
ceph auth get client.<id>
```

For example:


```
[root@monitor ~]# ceph auth get client.1
```

3. If you plan to use the kernel client, create a secret file using the key retrieved from the previous step.

On the client node, copy the string after **key =** into **/etc/ceph/ceph.client.<id>.secret**:

For example, if the client ID is **1** add a single line to **/etc/ceph/ceph.client.1.secret** with the key:

```
[root@client ~]# cat /etc/ceph/ceph.client.1.secret
AQBSdFhcGZFUDRAAcKhG9CI2HPiDMMRv4DC43A==
```



IMPORTANT

Do not include the space in between **key =** and the string or else mounting will not work.

4. If you plan to use the File System in User Space (FUSE) client, copy the keyring to the client.

- a. On the Monitor node, export the keyring to a file:

```
# ceph auth get client.<id> -o ceph.client.<id>.keyring
```

For example, if the client ID is **1**:

```
[root@monitor ~]# ceph auth get client.1 -o ceph.client.1.keyring
exported keyring for client.1
```

- b. Copy the client keyring from the Monitor node to the **/etc/ceph/** directory on the client node:


```
scp root@<monitor>:/root/ceph.client.1.keyring /etc/ceph/ceph.client.1.keyring
```

Replace **<monitor>** with the Monitor host name or IP, for example:

```
[root@client ~]# scp root@192.168.0.1:/root/ceph.client.1.keyring
/etc/ceph/ceph.client.1.keyring
```

5. Set the appropriate permissions for the keyring file.

```
chmod 644 <keyring>
```

Specify the path to the keyring, for example:

```
[root@client ~]# chmod 644 /etc/ceph/ceph.client.1.keyring
```


Additional Resources

- The [User Management](#) chapter in the *Administration Guide* for Red Hat Ceph Storage 3

3.4. MOUNTING THE CEPH FILE SYSTEM AS A KERNEL CLIENT

You can mount the Ceph File System as a kernel client:

- [Manually by using the `mount` command-line utility](#)
- [Automatically by adding an entry to the `/etc/fstab` file](#)



IMPORTANT

Clients on Linux distributions aside from Red Hat Enterprise Linux are permitted but not supported. If issues are found in the MDS or other parts of the cluster when using these clients, Red Hat will address them, but if the cause is found to be on the client side, the issue will have to be addressed by the kernel vendor.

3.4.1. Prerequisites

- On the client node, enable the Red Hat Ceph Storage 3 Tools repository:
 - On Red Hat Enterprise Linux, use:

```
[root@client ~]# subscription-manager repos --enable=rhel-7-server-rhceph-3-tools-rpms
```

- On Ubuntu, use:

```
[user@client ~]$ sudo bash -c 'umask 0077; echo deb
https://customername:customerpasswd@rhcs.download.redhat.com/3-updates/Tools
$(lsb_release -sc) main | tee /etc/apt/sources.list.d/Tools.list'
[user@client ~]$ sudo bash -c 'wget -O - https://www.redhat.com/security/fd431d51.txt |
apt-key add -'
[user@client ~]$ sudo apt-get update
```

- On the destination client node, create a new **etc/ceph** directory:

■

```
[root@client ~]# mkdir /etc/ceph
```

- Copy the Ceph configuration file from a Monitor node to the destination client node.

```
scp root@<monitor>:/etc/ceph/ceph.conf /etc/ceph/ceph.conf
```

Replace **<monitor>** with the Monitor host name or IP address, for example:

```
[root@client ~]# scp root@192.168.0.1:/etc/ceph/ceph.conf /etc/ceph/ceph.conf
```

- Set the correct owner and group on the **ceph.conf** file:

```
[root@client ~]# chown ceph:ceph /etc/ceph/ceph.conf
```

- Set the appropriate permissions for the configuration file:

```
[root@client ~]# chmod 644 /etc/ceph/ceph.conf
```

3.4.2. Manually Mounting the Ceph File System as a kernel Client

To manually mount the Ceph File System as a kernel client, use the **mount** utility.

Prerequisites

- A Ceph File System is created.
- The **ceph-common** package is installed.

Procedure

1. Create a mount directory:

```
mkdir -p <mount-point>
```

For example:

```
[root@client]# mkdir -p /mnt/cephfs
```

2. Mount the Ceph File System. To specify multiple Monitor addresses, either separate them with commas in the **mount** command, or configure a DNS server so that a single host name resolves to multiple IP addresses and pass that host name to the **mount** command. Set the user name and path to the secret file.

```
mount -t ceph <monitor1-host-name>:6789,<monitor2-host-name>:6789,<monitor3-host-name>:6789:/ <mount-point> -o name=<user-name>,secretfile=<path>
```

For example:

```
[root@client ~]# mount -t ceph mon1:6789,mon2:6789,mon3:6789:/mnt/cephfs -o name=1,secretfile=/etc/ceph/ceph.client.1.secret
```

3. Verify that the file system is successfully mounted:

```
stat -f <mount-point>
```

For example:

```
[root@client ~]# stat -f /mnt/cephfs
```

Additional Resources

- The **mount(8)** manual page
- The [DNS Servers](#) chapter in the Networking Guide for Red Hat Enterprise Linux 7
- The [User Management](#) chapter in the Administration Guide for Red Hat Ceph Storage 3

3.4.3. Automatically Mounting the Ceph File System as a kernel Client

To automatically mount a Ceph File System on start, edit the `/etc/fstab` file.

Prerequisites

- Consider to mount the file system manually first. See [Section 3.4.2, “Manually Mounting the Ceph File System as a kernel Client”](#) for details.
- If you want to use the `secretfile=` mounting option, install the **ceph-common** package.

Procedure

1. On the client host, create a new directory for mounting the Ceph File System.

```
mkdir -p <mount-point>
```

For example:

```
[root@client ~]# mkdir -p /mnt/cephfs
```

2. Edit the `/etc/fstab` file as follows:

```
#DEVICE          PATH          TYPE  OPTIONS
<host-name>:<port>:/, <mount-point> ceph  _netdev,
<host-name>:<port>:/,          [name=<user-name>,
<host-name>:<port>:/,          secret=<key>|
                              secretfile=<file>,
                              [<mount-options>]
```

In the first column, set the Monitor host names and their ports. Another way to specify multiple Monitor addresses is to configure a DNS server so that a single host name resolves to multiple IP addresses.

Set the mount point in the second column and the type to **ceph** in the third column.

Set the user name and secret file in the fourth column using the **name** and **secretfile** options, respectively.

Set the `_netdev` option to ensure that the file system is mounted after the networking subsystem to prevent networking issues. If you do not need access time information set `noatime` to increase performance.

For example:

```
#DEVICE    PATH          TYPE  OPTIONS
mon1:6789:/ /mnt/cephfs  ceph  _netdev, name=admin,
mon2:6789:/          secretfile=
mon3:6789:/          /home/secret.key,
noatime 00
```

The file system will be mounted on the next boot.

3.5. MOUNTING THE CEPH FILE SYSTEM AS A FUSE CLIENT

You can mount the Ceph File System as a File System in User Space (FUSE) client:

- Manually by using the `ceph-fuse` command-line utility
- Automatically by adding an entry to the `/etc/fstab` file

3.5.1. Prerequisites

- On the client node, enable the Red Hat Ceph Storage 3 Tools repository:
 - On Red Hat Enterprise Linux, use:

```
[root@client ~]# subscription-manager repos --enable=rhel-7-server-rhceph-3-tools-rpms
```

- On Ubuntu, use:

```
[user@client ~]$ sudo bash -c 'umask 0077; echo deb
https://customername:customerpasswd@rhcs.download.redhat.com/3-updates/Tools
$(lsb_release -sc) main | tee /etc/apt/sources.list.d/Tools.list'
[user@client ~]$ sudo bash -c 'wget -O - https://www.redhat.com/security/fd431d51.txt |
apt-key add -'
[user@client ~]$ sudo apt-get update
```

- Copy the client keyring to the client node. See [Section 3.3, “Creating Ceph File System Client Users”](#) for details.
- Copy the Ceph configuration file from a Monitor node to the client node.

```
scp root@<monitor>:/etc/ceph/ceph.conf /etc/ceph/ceph.conf
```

Replace `<monitor>` with the Monitor host name or IP, for example:

```
[root@client ~]# scp root@192.168.0.1:/etc/ceph/ceph.conf /etc/ceph/ceph.conf
```

- Set the appropriate permissions for the configuration file.

```
[root@client ~]# chmod 644 /etc/ceph/ceph.conf
```

3.5.2. Manually Mounting the Ceph File System as a FUSE Client

To mount a Ceph File System as a File System in User Space (FUSE) client, use the **ceph-fuse** utility.

Prerequisites

- On the node where the Ceph File System will be mounted, install the **ceph-fuse** package.
 - On Red Hat Enterprise Linux, use:

```
[root@client ~]# yum install ceph-fuse
```

- On Ubuntu, use:

```
[user@client ~]$ sudo apt-get install ceph-fuse
```

Procedure

1. Create a directory to serve as a mount point. Note that if you used the **path** option with MDS capabilities, the mount point must be within what is specified by **path**.

```
mkdir <mount-point>
```

For example:

```
[root@client ~]# mkdir /mnt/mycephfs
```

2. Use the **ceph-fuse** utility to mount the Ceph File System.

```
ceph-fuse -n client.<client-name> <mount-point>
```

For example:

```
[root@client ~]# ceph-fuse -n client.1 /mnt/mycephfs
```

- If you do not use the default name and location of the user keyring, that is **/etc/ceph/ceph.client.<client-name/id>.keyring**, use the **--keyring** option to specify the path to the user keyring, for example:

```
[root@client ~]# ceph-fuse -n client.1 --keyring=/etc/ceph/client.1.keyring /mnt/mycephfs
```

- If you restricted the client to a only mount and work within a certain directory, use the **-r** option to instruct the client to treat that path as its root:

```
ceph-fuse -n client.<client-name/id> <mount-point> -r <path>
```

For example, to instruct the client with ID **1** to treat the **/home/cephfs/** directory as its root:

```
[root@client ~]# ceph-fuse -n client.1 /mnt/cephfs -r /home/cephfs
```

3. Verify that the file system is successfully mounted:

```
stat -f <mount-point>
```

For example:

```
[user@client ~]$ stat -f /mnt/cephfs
```

Additional Resources

- The **ceph-fuse(8)** manual page *
- The [User Management](#) chapter in the *Administration Guide* for Red Hat Ceph Storage 3

3.5.3. Automatically Mounting the Ceph File System as a FUSE Client

To automatically mount a Ceph File System on start, edit the **/etc/fstab** file.

Prerequisites

- Consider to mount the file system manually first. See [Section 3.4.2, “Manually Mounting the Ceph File System as a kernel Client”](#) for details.

Procedure

1. On the client host, create a new directory for mounting the Ceph File System.

```
mkdir -p <mount-point>
```

For example:

```
[root@client ~]# mkdir -p /mnt/cephfs
```

2. Edit the **etc/fstab** file as follows:

```
#DEVICE  PATH      TYPE    OPTIONS
none     <mount-point> fuse.ceph _netdev
          ceph.id=<user-id>
          [,ceph.conf=<path>],
          defaults 0 0
```

Specify the use ID, for example **admin**, not **client-admin**, and the mount point. Use the **conf** option if you store the Ceph configuration file somewhere else than in the default location. In addition, specify required mount options. Consider to use the **_netdev** option that ensures that the file system is mounted after the networking subsystem to prevent networking issues. For example:

```
#DEVICE  PATH      TYPE    OPTIONS
none     /mnt/ceph fuse.ceph _netdev
          ceph.id=admin,
          ceph.conf=/etc/ceph/cluster.conf,
          defaults 0 0
```

The file system will be mounted on the next boot.

3.6. CREATING CEPH FILE SYSTEMS WITH ERASURE CODING

By default, Ceph uses replicated pools for data pools. You can also add an additional erasure-coded

data pool, if needed. Ceph File Systems (CephFS) backed by erasure-coded pools use less overall storage compared to Ceph File Systems backed by replicated pools. While erasure-coded pools use less overall storage, they also use more memory and processor resources than replicated pools.



IMPORTANT

Ceph File Systems on erasure-coded pools are a Technology Preview. For more information see [Erasure Coding with Overwrites \(Technology Preview\)](#).



IMPORTANT

Ceph File Systems on erasure-coded pools require pools using the BlueStore object store. For more information see [Erasure Coding with Overwrites \(Technology Preview\)](#).



IMPORTANT

Red Hat recommends to use the replicated pool as the default data pool.

Prerequisites

- A running Red Hat Ceph Storage Cluster.
- Pools using BlueStore OSDs.

Procedure

1. Create an erasure-coded data pool for Ceph File System:

```
ceph osd pool create $DATA_POOL $PG_NUM erasure
```

For example, to create an erasure-coded pool named **cephfs-data-ec** with 64 placement groups:

```
[root@monitor ~]# ceph osd pool create cephfs-data-ec 64 erasure
```

2. Create a replicated metadata pool for Ceph File System:

```
ceph osd pool create $METADATA_POOL $PG_NUM
```

For example, to create a pool named **cephfs-metadata** with 64 placement groups:

```
[root@monitor ~]# ceph osd pool create cephfs-metadata 64
```

3. Enable overwrites on the erasure-coded pool:


```
ceph osd pool set $DATA_POOL allow_ec_overwrites true
```

For example, to enable overwrites on an erasure-coded pool named **cephfs-data-ec**:

```
[root@monitor ~]# ceph osd pool set cephfs-data-ec allow_ec_overwrites true
```

4. Create the Ceph File System:

```
ceph fs new $FS_EC $METADATA_POOL $DATA_POOL
```



NOTE

Using an erasure-coded pool for the default data pool is discouraged, but you can use **--force** to override this default. Specify the name of the Ceph File System, and the metadata and data pools, for example:

```
[root@monitor ~]# ceph fs new cephfs-ec cephfs-metadata cephfs-data-ec --force
```

5. Verify that one or more MDSs enter the active state based on your configuration:

```
ceph fs status $FS_EC
```

Specify the name of the Ceph File System, for example:

```
[root@monitor ~]# ceph fs status cephfs-ec
cephfs-ec - 0 clients
=====
+-----+-----+-----+-----+-----+-----+
| Rank | State | MDS | Activity | dns | inos |
+-----+-----+-----+-----+-----+-----+
| 0 | active | node1 | Reqs: 0/s | 10 | 12 |
+-----+-----+-----+-----+-----+
+-----+-----+-----+-----+
| Pool | type | used | avail |
+-----+-----+-----+-----+
| cephfs-metadata | metadata | 4638 | 26.7G |
| cephfs-data-ec | data | 0 | 26.7G |
+-----+-----+-----+-----+

+-----+
| Standby MDS |
+-----+
| node3 |
| node2 |
+-----+
```

6. If you want to add an additional erasure-coded pool, as data pool, to the existing file system,:
 - a. Create an erasure-coded data pool for Ceph File System:

```
ceph osd pool create $DATA_POOL $PG_NUM erasure
```

For example, to create an erasure-coded pool named **cephfs-data-ec1** with 64 placement groups:

```
[root@monitor ~]# ceph osd pool create cephfs-data-ec1 64 erasure
```

- b. Enable overwrites on the erasure-coded pool:


```
ceph osd pool set $DATA_POOL allow_ec_overwrites true
```

For example, to enable overwrites on an erasure-coded pool named **cephfs-data-ec1**:

```
[root@monitor ~]# ceph osd pool set cephfs-data-ec1 allow_ec_overwrites true
```

- c. Add the newly created pool to an existing Ceph File System:

```
ceph fs add_data_pool $FS_EC $DATA_POOL
```

For example, to add an erasure-coded pool named **cephfs-data-ec1**:

```
[root@monitor ~]# ceph fs add_data_pool cephfs-ec cephfs-data-ec1
```

- d. Verify that one or more MDSs enter the active state based on your configuration.

```
ceph fs status $FS_EC
```

Specify the name of the Ceph File System, for example:

```
[root@monitor ~]# ceph fs status cephfs-ec
cephfs-ec - 0 clients
=====
+-----+-----+-----+-----+-----+-----+
| Rank | State | MDS | Activity | dns | inos |
+-----+-----+-----+-----+-----+-----+
| 0 | active | node1 | Reqs: 0/s | 10 | 12 |
+-----+-----+-----+-----+-----+
| Pool | type | used | avail |
+-----+-----+-----+-----+
| cephfs-metadata | metadata | 4638 | 26.7G |
| cephfs-data-ec | data | 0 | 26.7G |
| cephfs-data-ec1 | data | 0 | 26.7G |
+-----+-----+-----+-----+

+-----+
| Standby MDS |
+-----+
| node3 |
| node2 |
+-----+
```

Additional Resources

- See the [Erasure-Coded Pools](#) section in the Red Hat Ceph Storage *Storage Strategies Guide* for more information.
- See the [Erasure Coding with Overwrites](#) section in the Red Hat Ceph Storage *Storage Strategies Guide* for more information.

CHAPTER 4. ADMINISTERING CEPH FILE SYSTEMS

This chapter describes common Ceph File System administrative tasks.

- To map a directory to a particular MDS rank, see [Section 4.2, “Mapping Directory Trees to MDS Ranks”](#).
- To disassociate a directory from a MDS rank, see [Section 4.3, “Disassociating Directory Trees from MDS Ranks”](#).
- To work with files and directory layouts, see [Section 4.4, “Working with File and Directory Layouts”](#).
- To add a new data pool, see [Section 4.5, “Adding Data Pools”](#).
- To work with quotas, see [Section 4.6, “Working with Ceph File System quotas”](#).
- To remove a Ceph File System, see [Section 4.7, “Removing Ceph File Systems”](#).

4.1. PREREQUISITES

- Deploy a Ceph Storage Cluster if you do not have one. For details, see the [Installation Guide for Red Hat Enterprise Linux](#) or [Ubuntu](#).
- Install and configure Ceph Metadata Server daemons (**ceph-mds**). For details, see the [Installation Guide for Red Hat Enterprise Linux](#) or [Ubuntu Chapter 2, Configuring Metadata Server Daemons](#).
- Create and mount the Ceph File System. For details, see [Chapter 3, Deploying Ceph File Systems](#).

4.2. MAPPING DIRECTORY TREES TO MDS RANKS

This section describes how to map a directory and its subdirectories to a particular active Metadata Server (MDS) rank so that its metadata is only managed by the MDS daemon holding that rank. This approach enables you to evenly spread application load or limit impact of users' metadata requests to the entire cluster.



IMPORTANT

Note that an internal balancer already dynamically spreads the application load. Therefore, map directory trees to ranks only for certain carefully chosen applications. In addition, when a directory is mapped to a rank, the balancer cannot split it. Consequently, a large number of operations within the mapped directory can overload the rank and the MDS daemon that manages it.

Prerequisites

- Configure multiple active MDS daemons. See [Section 2.6, “Configuring Multiple Active Metadata Server Daemons”](#) for details.
- Ensure that the **attr** package is installed on the client node with mounted Ceph File System.

Procedure

1. Create a new directory tree on the client node:

- Set the **ceph.dir.pin** extended attribute on a directory.

```
setfattr -n ceph.dir.pin -v <rank> <directory>
```

For example, to assign the **/home/ceph-user/** directory all of its subdirectories to rank 2:

```
[user@client ~]$ setfattr -n ceph.dir.pin -v 2 /home/ceph-user
```

Additional Resources

- [Section 4.3, “Disassociating Directory Trees from MDS Ranks”](#)

4.3. DISASSOCIATING DIRECTORY TREES FROM MDS RANKS

This section describes how to disassociate a directory from a particular active Metadata Server (MDS) rank.

Prerequisites

- Ensure that the **attr** package is installed on the client node with mounted Ceph File System.

Procedure

- Set the **ceph.dir.pin** extended attribute to -1 on a directory.

```
setfattr -n ceph.dir.pin -v -1 <directory>
```

For example, to disassociate the **/home/ceph-user/** directory from a MDS rank:

```
[user@client ~]$ setfattr -n ceph.dir.pin -v -1 /home/ceph-user
```

Note that any separately mapped subdirectories of **/home/ceph-user/** are not affected.

Additional Resources

- [Section 4.2, “Mapping Directory Trees to MDS Ranks”](#)

4.4. WORKING WITH FILE AND DIRECTORY LAYOUTS

This section describes how to:

- [Understand file and directory layouts](#)
- [Set the layouts](#)
- [View the layouts](#)
- [Remove the directory layouts](#)

4.4.1. Prerequisites

- Make sure that the **attr** package is installed.

4.4.2. Understanding File and Directory Layouts

This section explains what file and directory layouts are in the context for the Ceph File System.

A layout of a file or directory controls how its content is mapped to Ceph RADOS objects. The directory layouts serves primarily for setting an inherited layout for new files in that directory. See [Layouts Inheritance](#) for more details.

To view and set a file or directory layout, use virtual extended attributes or extended file attributes (**xattrs**). The name of the layout attributes depends on whether a file is a regular file or a directory:

- Regular files layout attributes are called **ceph.file.layout**
- Directories layout attributes are called **ceph.dir.layout**

The [File and Directory Layout Fields](#) table lists available layout fields that you can set on files and directories.

Table 4.1. File and Directory Layout Fields

Field	Description	Type
pool	ID or name of the pool to store file's data objects. Note that the pool must part of the set of data pools of the Ceph file system. See Section 4.5, "Adding Data Pools" for details.	string
pool_namespace	Namespace to write objects to. Empty by default, that means the default namespace is used.	string
stripe_unit	The size in bytes of a block of data used in the RAID 0 distribution of a file. All stripe units for a file have equal size. The last stripe unit is typically incomplete. That means it represents the data at the end of the file as well as unused space beyond it up to the end of the fixed stripe unit size.	integer
stripe_count	The number of consecutive stripe units that constitute a RAID 0 "stripe" of file data.	integer
object_size	Size of RADOS objects in bytes in which file data are chunked.	integer

Layouts Inheritance

Files inherit the layout of their parent directory when you create them. However, subsequent changes to the parent directory layout do not affect children. If a directory does not have any layouts set, files inherit the layout from the closest directory with layout in the directory structure.

4.4.3. Setting File and Directory Layouts

Use the **setfattr** command to set layout fields on a file or directory.



IMPORTANT

When you modify the layout fields of a file, the file must be empty, otherwise an error occurs.

Procedure

- To modify layout fields on a file or directory:

```
setfattr -n ceph.<type>.layout.<field> -v <value> <path>
```

Replace:

- **<type>** with **file** or **dir**
- **<field>** with the name of the field, see the [File and Directory Layouts Fields](#) table for details.
- **<value>** with the new value of the field
- **<path>** with the path to the file or directory

For example, to set the **stripe_unit** field to **1048576** on the **test** file:

```
$ setfattr -n ceph.file.layout.stripe_unit -v 1048576 test
```

Additional Resources

- The **setfattr(1)** manual page

4.4.4. Viewing File and Directory Layouts

This section describes how to use the **getfattr** command to view layout fields on a file or directory.

Procedure

- To view layout fields on a file or directory as a single string:

```
getfattr -n ceph.<type>.layout <path>
```

Replace * **<path>** with the path to the file or directory * **<type>** with **file** or **dir**

For example, to view file layouts on the **/home/test/** file:

```
$ getfattr -n ceph.dir.layout /home/test
ceph.dir.layout="stripe_unit=4194304 stripe_count=2 object_size=4194304
pool=cephfs_data"
```



NOTE

Directories do not have an explicit layout until you set it (see [Section 4.4.3, “Setting File and Directory Layouts”](#)). Consequently, an attempt to view the layout fails if you never modified the layout.

- To view individual layout fields on a file or directory:


```
getfattr -n ceph.<type>.layout.<field> <path>
```

Replace:

- **<type>** with **file** or **dir**
- **<field>** with the name of the field, see the [File and Directory Layouts Fields](#) table for details.
- **<path>** with the path to the file or directory

For example, to view the **pool** field of the **test** file:

```
$ getfattr -n ceph.file.layout.pool test
ceph.file.layout.pool="cephfs_data"
```



NOTE


When viewing the **pool** field, the pool is usually indicated by its name. However, when you just created the pool, it can be indicated by its ID.

Additional Resources

- The **getfattr(1)** manual page

4.4.5. Removing Directory Layouts

This section describes how to use the **setfattr** command to remove layouts from a directory.



NOTE

When you set a file layout, you cannot change or remove it.

Procedure

- To remove a layout from a directory:

```
setfattr -x ceph.dir.layout <path>
```

Replace:

- **<path>** with the path to the directory

For example:

```
$ setfattr -x ceph.dir.layout /home/cephfs
```

- To remove the **pool_namespace** field:


```
$ setfattr -x ceph.dir.layout.pool_namespace <directory>
```

Replace:

- **<path>** with the path to the directory

For example:

```
$ setfattr -x ceph.dir.layout.pool_namespace /home/cephfs
```



NOTE

The **pool_namespace** field is the only field you can remove separately.

Additional Resources

- The **setfattr(1)** manual page

4.5. ADDING DATA POOLS

The Ceph File System (CephFS) supports adding more than one pool to be used for storing data. This can be useful for:

- Storing log data on reduced redundancy pools
- Storing user home directories on an SSD or NVMe pool
- Basic data segregation.

Before using another data pool in the Ceph File System, you must add it as described in this section.

By default, for storing file data, CephFS uses the initial data pool that was specified during its creation. To use a secondary data pool, you must also configure a part of the file system hierarchy to store file data in that pool (and optionally, within a namespace of that pool) using file and directory layouts. See [Section 4.4, “Working with File and Directory Layouts”](#) for details.

Procedure

Use the following commands from a Monitor host and as the **root** user.

1. Create a new data pool.

```
ceph osd pool create <name> <pg_num>
```

Replace:

- **<name>** with the name of the pool
- **<pg_num>** with the number of placement groups (PGs)

For example:

```
[root@monitor]# ceph osd pool create cephfs_data_ssd 64
pool 'cephfs_data_ssd' created
```

2. Add the newly created pool under the control of the Metadata Servers.

```
ceph mds add_data_pool <name>
```

Replace:

- **<name>** with the name of the pool

For example:

```
[root@monitor]# ceph mds add_data_pool cephfs_data_ssd
added data pool 6 to fsmap
```

3. Verify that the pool was successfully added:

```
[root@monitor]# ceph fs ls
name: cephfs, metadata pool: cephfs_metadata, data pools: [cephfs_data cephfs_data_ssd]
```

4. If you use the **cephx** authentication, make sure that clients can access the new pool. See [Section 3.3, "Creating Ceph File System Client Users"](#) for details.

4.6. WORKING WITH CEPH FILE SYSTEM QUOTAS

As a storage administrator, you can view, set, and remove quotas on any directory in the file system. You can place quota restrictions on the number of bytes or the number of files within the directory.

4.6.1. Prerequisites

- Make sure that the **attr** package is installed.

4.6.2. Ceph File System quotas

This section describes the properties of quotas and their limitations in CephFS.

Understanding quota limitations

- CephFS quotas rely on the cooperation of the client mounting the file system to stop writing data when it reaches the configured limit. However, quotas alone cannot prevent an adversarial, untrusted client from filling the file system.
- Once processes that write data to the file system reach the configured limit, a short period of time elapses between when the amount of data reaches the quota limit, and when the processes stop writing data. The time period generally measures in the tenths of seconds. However, processes continue to write data during that time. The amount of additional data that the processes write depends on the amount of time elapsed before they stop.
- Linux kernel clients version 4.17 and higher use the userspace client, libcephfs and ceph-fuse to support CephFS quotas. However, those kernel clients only support quotas on mimic+ clusters. Kernel clients, even recent versions, cannot manage quotas on older storage clusters, even if they can set the quotas' extended attributes.
- When using path-based access restrictions, be sure to configure the quota on the directory to which the client is restricted, or to a directory nested beneath it. If the client has restricted access to a specific path based on the MDS capability, and the quota is configured on an ancestor directory that the client cannot access, the client will not enforce the quota. For example, if the client cannot access the **/home/** directory and the quota is configured on **/home/**, the client cannot enforce that quota on the directory **/home/user/**.
- Snapshot file data that has been deleted or changed does not count towards the quota. See also: <http://tracker.ceph.com/issues/24284>

4.6.3. Viewing quotas

This section describes how to use the **getfattr** command and the **ceph.quota** extended attributes to view the quota settings for a directory.



NOTE

If the attributes appear on a directory inode, then that directory has a configured quota. If the attributes do not appear on the inode, then the directory does not have a quota set, although its parent directory might have a quota configured. If the value of the extended attribute is 0, the quota is not set.

Prerequisites

- Make sure that the **attr** package is installed.

Procedure

1. To view CephFS quotas.
 - a. Using a byte-limit quota:

Syntax

```
getfattr -n ceph.quota.max_bytes DIRECTORY
```

Example

```
[root@fs ~]# getfattr -n ceph.quota.max_bytes /cephfs/
```

- b. Using a file-limit quota:

Syntax

```
getfattr -n ceph.quota.max_files DIRECTORY
```

Example

```
[root@fs ~]# getfattr -n ceph.quota.max_files /cephfs/
```

Additional Resources

- See the **getfattr(1)** manual page for more information.

4.6.4. Setting quotas

This section describes how to use the **setfattr** command and the **ceph.quota** extended attributes to set the quota for a directory.

Prerequisites

- Make sure that the **attr** package is installed.

Procedure

1. To set CephFS quotas.
 - a. Using a byte-limit quota:

Syntax

```
setfattr -n ceph.quota.max_bytes -v 100000000 /some/dir
```

Example

```
[root@fs ~]# setfattr -n ceph.quota.max_bytes -v 100000000 /cephfs/
```

In this example, 100000000 bytes equals 100 MB.

- b. Using a file-limit quota:

Syntax

```
setfattr -n ceph.quota.max_files -v 10000 /some/dir
```

Example

```
[root@fs ~]# setfattr -n ceph.quota.max_files -v 10000 /cephfs/
```

In this example, 10000 equals 10,000 files.

Additional Resources

- See the **setfattr(1)** manual page for more information.

4.6.5. Removing quotas

This section describes how to use the **setfattr** command and the **ceph.quota** extended attributes to remove a quota from a directory.

Prerequisites

- Make sure that the **attr** package is installed.

Procedure

1. To remove CephFS quotas.
 - a. Using a byte-limit quota:

Syntax

```
setfattr -n ceph.quota.max_bytes -v 0 DIRECTORY
```

Example

■

```
[root@fs ~]# setfattr -n ceph.quota.max_bytes -v 0 /cephfs/
```

- b. Using a file-limit quota:

Syntax

```
setfattr -n ceph.quota.max_files -v 0 DIRECTORY
```

Example

```
[root@fs ~]# setfattr -n ceph.quota.max_files -v 0 /cephfs/
```

Additional Resources

- See the **setfattr(1)** manual page for more information.

4.6.6. Additional Resources

- See the **getfattr(1)** manual page for more information.
- See the **setfattr(1)** manual page for more information.

4.7. REMOVING CEPH FILE SYSTEMS

As a storage administrator, you can remove a Ceph File System (CephFS). Before doing so, consider backing up all the data and verifying that all clients have unmounted the file system locally.



WARNING

This operation is destructive and will make the data stored on the Ceph File System permanently inaccessible.

Prerequisites

- Back up your data.
- Access as the **root** user to a Ceph Monitor node.

Procedure

1. Mark the cluster down.

```
ceph fs set name cluster_down true
```

Replace:

- *name* with the name of the Ceph File System you want to remove

For example:

```
[root@monitor]# ceph fs set cephfs cluster_down true
marked down
```

2. Display the status of the Ceph File System.

```
ceph fs status
```

For example:

```
[root@monitor]# ceph fs status
cephfs - 0 clients
=====
+-----+-----+-----+-----+-----+-----+
| Rank | State | MDS | Activity | dns | inos |
+-----+-----+-----+-----+-----+-----+
| 0 | active | ceph4 | Reqs: 0 /s | 10 | 12 |
+-----+-----+-----+-----+-----+
+-----+-----+-----+-----+
| Pool | type | used | avail |
+-----+-----+-----+-----+
| cephfs_metadata | metadata | 2246 | 975G |
| cephfs_data | data | 0 | 975G |
+-----+-----+-----+-----+
```

3. Fail all MDS ranks shown in the status.

```
# ceph mds fail rank
```

Replace:

- *rank* with the rank of the MDS daemons to fail

For example:

```
[root@monitor]# ceph mds fail 0
```

4. Remove the Ceph File System.

```
ceph fs rm name --yes-i-really-mean-it
```

Replace:

- *name* with the name of the Ceph File System you want to remove

For example:

```
[root@monitor]# ceph fs rm cephfs --yes-i-really-mean-it
```

5. Verify that the file system has been successfully removed.

```
[root@monitor]# ceph fs ls
```

6. Optional. Remove data and metadata pools associated with the removed file system. See the [Delete a pool](#) section in the Red Hat Ceph Storage 3 *Storage Strategies Guide*.

CHAPTER 5. UNMOUNTING CEPH FILE SYSTEMS

This chapter describes how to unmount Ceph File System mounted as kernel or File System in User Space (FUSE) clients.

5.1. UNMOUNTING CEPH FILE SYSTEMS MOUNTED AS KERNEL CLIENTS

This section shows how to unmount a Ceph File System that is mounted as a kernel client.

Procedure

- To unmount a Ceph File System mounted as a kernel client:

```
umount <mount-point>
```

Specify the mount point where the file system is mounted:

```
[root@client ~]# umount /mnt/cephfs
```

Additional Resources

- The **umount(8)** manual page

5.2. UNMOUNTING CEPH FILE SYSTEMS MOUNTED AS FUSE CLIENTS

This section shows how to unmount a Ceph File System that is mounted as a File System in User Space (FUSE) client.

Procedure

- To unmount a Ceph File System mounted in FUSE:

```
fusermount -u <mount-point>
```

Specify the mount point where the file system is mounted

```
[root@client ~]# fusermount -u /mnt/cephfs
```

Additional Resources

- The **ceph-fuse(8)** manual page

APPENDIX A. TROUBLESHOOTING

A.1. CEPHFS HEALTH MESSAGES

Cluster health checks

The Ceph monitor daemons generate health messages in response to certain states of the MDS cluster. Below is the list of the cluster health messages and their explanation.

mds rank(s) <ranks> have failed

One or more MDS ranks are not currently assigned to any MDS daemon. The cluster will not recover until a suitable replacement daemon starts.

mds rank(s) <ranks> are damaged

One or more MDS ranks has encountered severe damage to its stored metadata, and cannot start again until the metadata is repaired.

mds cluster is degraded

One or more MDS ranks are not currently up and running, clients might pause metadata I/O until this situation is resolved. This includes ranks being failed or damaged, and additionally includes ranks which are running on an MDS but are not in the **active** state yet, for example ranks in the **replay** state.

mds <names> are laggy

The MDS daemons are supposed to send beacon messages to the monitor in an interval specified by the **mds_beacon_interval** option (default is 4 seconds). If an MDS daemon fails to send a message within the time specified by the **mds_beacon_grace** option (default is 15 seconds), the Ceph monitor marks the MDS daemon as **laggy** and automatically replaces it with a standby daemon if any is available.

Daemon-reported health checks

The MDS daemons can identify a variety of unwanted conditions, and return them in the output of the **ceph status** command. This conditions have human readable messages, and additionally a unique code starting **MDS_HEALTH** which appears in JSON output. Below is the list of the daemon messages, their codes and explanation.

"Behind on trimming..."

Code: MDS_HEALTH_TRIM

CephFS maintains a metadata journal that is divided into log segments. The length of journal (in number of segments) is controlled by the **mds_log_max_segments** setting. When the number of segments exceeds that setting, the MDS starts writing back metadata so that it can remove (trim) the oldest segments. If this process is too slow, or a software bug is preventing trimming, then this health message appears. The threshold for this message to appear is for the number of segments to be double **mds_log_max_segments**.

"Client <name> failing to respond to capability release"

Code: MDS_HEALTH_CLIENT_LATE_RELEASE,
MDS_HEALTH_CLIENT_LATE_RELEASE_MANY

CephFS clients are issued capabilities by the MDS. The capabilities work like locks. Sometimes, for example when another client needs access, the MDS requests clients to release their capabilities. If the client is unresponsive, it might fail to do so promptly or fail to do so at all. This message appears if a client has taken a longer time to comply than the time specified by the **mds_revoke_cap_timeout** option (default is 60 seconds).

"Client <name> failing to respond to cache pressure"

Code: MDS_HEALTH_CLIENT_RECALL, MDS_HEALTH_CLIENT_RECALL_MANY

Clients maintain a metadata cache. Items, such as inodes, in the client cache are also pinned in the MDS cache. When the MDS needs to shrink its cache to stay within its own cache size limits, the MDS sends messages to clients to shrink their caches too. If a client is unresponsive, it can prevent the MDS from properly staying within its cache size and the MDS might eventually run out of memory and terminate unexpectedly. This message appears if a client has taken more time to comply than the time specified by the **mds_recall_state_timeout** option (default is 60 seconds). See [Section 2.8, "Understanding MDS Cache Size Limits"](#) for details.

"Client name failing to advance its oldest client/flush tid"

Code: MDS_HEALTH_CLIENT_OLDEST_TID, MDS_HEALTH_CLIENT_OLDEST_TID_MANY

The CephFS protocol for communicating between clients and MDS servers uses a field called **oldest tid** to inform the MDS of which client requests are fully complete so that the MDS can forget about them. If an unresponsive client is failing to advance this field, the MDS might be prevented from properly cleaning up resources used by client requests. This message appears if a client have more requests than the number specified by the **max_completed_requests** option (default is 100000) that are complete on the MDS side but have not yet been accounted for in the client's **oldest tid** value.

"Metadata damage detected"

Code: MDS_HEALTH_DAMAGE

Corrupt or missing metadata was encountered when reading from the metadata pool. This message indicates that the damage was sufficiently isolated for the MDS to continue operating, although client accesses to the damaged subtree return I/O errors. Use the **damage ls** administration socket command to view details on the damage. This message appears as soon as any damage is encountered.

"MDS in read-only mode"

Code: MDS_HEALTH_READ_ONLY

The MDS has entered into read-only mode and will return the **EROFS** error codes to client operations that attempt to modify any metadata. The MDS enters into read-only mode:

- If it encounters a write error while writing to the metadata pool.
- If the administrator forces the MDS to enter into read-only mode by using the **force_readonly** administration socket command.

"<N> slow requests are blocked"

Code: MDS_HEALTH_SLOW_REQUEST

One or more client requests have not been completed promptly, indicating that the MDS is either running very slowly, or encountering a bug. Use the **ops** administration socket command to list outstanding metadata operations. This message appears if any client requests have taken longer time than the value specified by the **mds_op_complaint_time** option (default is 30 seconds).

"Too many inodes in cache"

Code: MDS_HEALTH_CACHE_OVERSIZED

The MDS has failed to trim its cache to comply with the limit set by the administrator. If the MDS cache becomes too large, the daemon might exhaust available memory and terminate unexpectedly. This message appears if the MDS cache size is 50% greater than its limit (by default). See [Section 2.8, "Understanding MDS Cache Size Limits"](#) for details.

APPENDIX B. CONFIGURATION REFERENCE

B.1. MDS CONFIGURATION REFERENCE

mon force standby active

Description

If set to **true**, monitors force MDS in standby replay mode to be active. Set under the **[mon]** or **[global]** section in the Ceph configuration file.

Type

Boolean

Default

true

max mds

Description

The number of active MDS daemons during cluster creation. Set under the **[mon]** or **[global]** section in the Ceph configuration file.

Type

32-bit Integer

Default

1

mds max file size

Description

The maximum allowed file size to set when creating a new file system.

Type

64-bit Integer Unsigned

Default

1ULL << 40

mds cache memory limit

Description

The memory limit the MDS enforces for its cache. Red Hat recommends to use this parameter instead of the **mds cache size** parameter.

Type

64-bit Integer Unsigned

Default

1073741824

mds cache reservation

Description

The cache reservation (memory or inodes) for the MDS cache to maintain. The value is a percentage of the maximum cache configured. Once the MDS begins dipping into its reservation, it recalls client state until its cache size shrinks to restore the reservation.

Type

Float

Default**0.05****mds cache size****Description**

The number of inodes to cache. A value of 0 indicates an unlimited number. Red Hat recommends to use the **mds_cache_memory_limit** to limit the amount of memory the MDS cache uses.

Type

32-bit Integer

Default**0****mds cache mid****Description**

The insertion point for new items in the cache LRU (from the top).

Type

Float

Default**0.7****mds dir commit ratio****Description**

The fraction of directory contains erroneous information before Ceph commits using a full update (instead of partial update).

Type

Float

Default**0.5****mds dir max commit size****Description**

The maximum size of a directory update before Ceph breaks the directory into smaller transactions (in MB).

Type

32-bit Integer

Default**90****mds decay halflife****Description**

The half-life of MDS cache temperature.

Type

Float

Default

5

mds beacon interval

Description

The frequency (in seconds) of beacon messages sent to the monitor.

Type

Float

Default

4

mds beacon grace

Description

The interval without beacons before Ceph declares an MDS **laggy** (and possibly replace it).

Type

Float

Default

15

mds blacklist interval

Description

The blacklist duration for failed MDS daemons in the OSD map.

Type

Float

Default

24.0*60.0

mds session timeout

Description

The interval (in seconds) of client inactivity before Ceph times out capabilities and leases.

Type

Float

Default

60

mds session autoclose

Description

The interval (in seconds) before Ceph closes a **laggy** client's session.

Type

Float

Default

300

mds reconnect timeout**Description**

The interval (in seconds) to wait for clients to reconnect during MDS restart.

Type

Float

Default

45

mds tick interval**Description**

How frequently the MDS performs internal periodic tasks.

Type

Float

Default

5

mds dirstat min interval**Description**

The minimum interval (in seconds) to try to avoid propagating recursive statistics up the tree.

Type

Float

Default

1

mds scatter nudge interval**Description**

How quickly changes in directory statistics propagate up.

Type

Float

Default

5

mds client prealloc inos**Description**

The number of inode numbers to preallocate per client session.

Type

32-bit Integer

Default

1000

mds early reply**Description**

Determines whether the MDS allows clients to see request results before they commit to the journal.

Type

Boolean

Default

true

mds use tmap**Description**

Use **trivialmap** for directory updates.

Type

Boolean

Default

true

mds default dir hash**Description**

The function to use for hashing files across directory fragments.

Type

32-bit Integer

Default

2 (that is, **rjenkins**)

mds log**Description**

Set to **true** if the MDS should journal metadata updates (disabled for benchmarking only).

Type

Boolean

Default

true

mds log skip corrupt events**Description**

Determines whether the MDS tries to skip corrupt journal events during journal replay.

Type

Boolean

Default

false

mds log max events**Description**

The maximum events in the journal before Ceph initiates trimming. Set to **-1** to disable limits.

Type

32-bit Integer

Default

-1

mds log max segments

Description

The maximum number of segments (objects) in the journal before Ceph initiates trimming. Set to **-1** to disable limits.

Type

32-bit Integer

Default

30

mds log max expiring

Description

The maximum number of segments to expire in parallels.

Type

32-bit Integer

Default

20

mds log eopen size

Description

The maximum number of inodes in an **EOpen** event.

Type

32-bit Integer

Default

100

mds bal sample interval

Description

Determines how frequently to sample directory temperature (for fragmentation decisions).

Type

Float

Default

3

mds bal replicate threshold

Description

The maximum temperature before Ceph attempts to replicate metadata to other nodes.

Type

Float

Default

8000**mds bal unreplicate threshold****Description**

The minimum temperature before Ceph stops replicating metadata to other nodes.

Type

Float

Default

0

mds bal frag**Description**

Determines whether the MDS will fragment directories.

Type

Boolean

Default

false

mds bal split size**Description**

The maximum directory size before the MDS will split a directory fragment into smaller bits.

Type

32-bit Integer

Default

10000

mds bal split rd**Description**

The maximum directory read temperature before Ceph splits a directory fragment.

Type

Float

Default

25000

mds bal split wr**Description**

The maximum directory write temperature before Ceph splits a directory fragment.

Type

Float

Default

10000

mds bal split bits

Description

The number of bits by which to split a directory fragment.

Type

32-bit Integer

Default

3

mds bal merge size**Description**

The minimum directory size before Ceph tries to merge adjacent directory fragments.

Type

32-bit Integer

Default

50

mds bal merge rd**Description**

The minimum read temperature before Ceph merges adjacent directory fragments.

Type

Float

Default

1000

mds bal merge wr**Description**

The minimum write temperature before Ceph merges adjacent directory fragments.

Type

Float

Default

1000

mds bal interval**Description**

The frequency (in seconds) of workload exchanges between MDS nodes.

Type

32-bit Integer

Default

10

mds bal fragment interval**Description**

The frequency (in seconds) of adjusting directory fragmentation.

Type

32-bit Integer

Default

5

mds bal idle threshold

Description

The minimum temperature before Ceph migrates a subtree back to its parent.

Type

Float

Default

0

mds bal max

Description

The number of iterations to run balancer before Ceph stops. Used for testing purposes only.

Type

32-bit Integer

Default

-1

mds bal max until

Description

The number of seconds to run balancer before Ceph stops. Used for testing purposes only.

Type

32-bit Integer

Default

-1

mds bal mode

Description

The method for calculating MDS load:

- **1** = Hybrid.
- **2** = Request rate and latency.
- **3** = CPU load.

Type

32-bit Integer

Default

0

mds bal min rebalance

Description

The minimum subtree temperature before Ceph migrates.

Type

Float

Default

0.1

mds bal min start**Description**

The minimum subtree temperature before Ceph searches a subtree.

Type

Float

Default

0.2

mds bal need min**Description**

The minimum fraction of target subtree size to accept.

Type

Float

Default

0.8

mds bal need max**Description**

The maximum fraction of target subtree size to accept.

Type

Float

Default

1.2

mds bal midchunk**Description**

Ceph will migrate any subtree that is larger than this fraction of the target subtree size.

Type

Float

Default

0.3

mds bal minchunk**Description**

Ceph will ignore any subtree that is smaller than this fraction of the target subtree size.

Type

Float

Default**0.001****mds bal target removal min****Description**

The minimum number of balancer iterations before Ceph removes an old MDS target from the MDS map.

Type

32-bit Integer

Default**5****mds bal target removal max****Description**

The maximum number of balancer iterations before Ceph removes an old MDS target from the MDS map.

Type

32-bit Integer

Default**10****mds replay interval****Description**

The journal poll interval when in **standby-replay** mode (**hot standby**).

Type

Float

Default**1****mds shutdown check****Description**

The interval for polling the cache during MDS shutdown.

Type

32-bit Integer

Default**0****mds thrash exports****Description**

Ceph will randomly export subtrees between nodes (testing only).

Type

32-bit Integer

Default**0**

mds thrash fragments**Description**

Ceph will randomly fragment or merge directories.

Type

32-bit Integer

Default

0

mds dump cache on map**Description**

Ceph will dump the MDS cache contents to a file on each MDS map.

Type

Boolean

Default

false

mds dump cache after rejoin**Description**

Ceph will dump MDS cache contents to a file after rejoining the cache during recovery.

Type

Boolean

Default

false

mds verify scatter**Description**

Ceph will assert that various scatter/gather invariants are **true** (for developers only).

Type

Boolean

Default

false

mds debug scatterstat**Description**

Ceph will assert that various recursive statistics invariants are **true** (for developers only).

Type

Boolean

Default

false

mds debug frag**Description**

Ceph will verify directory fragmentation invariants when convenient (for developers only).

Type

Boolean

Default**false****mds debug auth pins****Description**

The debug authentication pin invariants (for developers only).

Type

Boolean

Default**false****mds debug subtrees****Description**

The debug subtree invariants (for developers only).

Type

Boolean

Default**false****mds kill mdstable at****Description**

Ceph will inject MDS failure in MDS Table code (for developers only).

Type

32-bit Integer

Default**0****mds kill export at****Description**

Ceph will inject MDS failure in the subtree export code (for developers only).

Type

32-bit Integer

Default**0****mds kill import at****Description**

Ceph will inject MDS failure in the subtree import code (for developers only).

Type

32-bit Integer

Default

0**mds kill link at****Description**

Ceph will inject MDS failure in hard link code (for developers only).

Type

32-bit Integer

Default**0****mds kill rename at****Description**

Ceph will inject MDS failure in the rename code (for developers only).

Type

32-bit Integer

Default**0****mds wipe sessions****Description**

Ceph will delete all client sessions on startup (for testing only).

Type

Boolean

Default**0****mds wipe ino prealloc****Description**

Ceph will delete inode preallocation metadata on startup (for testing only).

Type

Boolean

Default**0****mds skip ino****Description**

The number of inode numbers to skip on startup (for testing only).

Type

32-bit Integer

Default**0****mds standby for name**

Description

The MDS daemon will standby for another MDS daemon of the name specified in this setting.

Type

String

Default

N/A

mds standby for rank**Description**

An instance of the MDS daemon will be standby for another MDS daemon instance of this rank.

Type

32-bit Integer

Default

-1

mds standby replay**Description**

Determines whether the MDS daemon polls and replays the log of an active MDS (**hot standby**).

Type

Boolean

Default

false

B.2. JOURNALER CONFIGURATION REFERENCE

journaler allow split entries**Description**

Allow an entry to span a stripe boundary.

Type

Boolean

Required

No

Default

true

journaler write head interval**Description**

How frequently to update the journal head object.

Type

Integer

Required

No

Default**15****journaler prefetch periods****Description**

How many stripe periods to read ahead on journal replay.

Type

Integer

Required

No

Default**10****journal prezero periods****Description**

How many stripe periods to zero ahead of write position.

Type

Integer

Required

No

Default**10****journaler batch interval****Description**

Maximum additional latency in seconds to incur artificially.

Type

Double

Required

No

Default**.001****journaler batch max****Description**

Maximum bytes that will be delayed flushing.

Type

64-bit Unsigned Integer

Required

No

Default**0**

B.3. FUSE CLIENT CONFIGURATION REFERENCE

This section lists configuration options for CephFS FUSE clients. Set them in the Ceph configuration file under the **[client]** section.

client_acl_type

Description

Set the ACL type. Currently, only possible value is **posix_acl** to enable POSIX ACL, or an empty string. This option only takes effect when **fuse_default_permissions** is set to **false**.

Type

String

Default

"" (no ACL enforcement)

client_cache_mid

Description

Set the client cache midpoint. The midpoint splits the least recently used lists into a hot and warm list.

Type

Float

Default

0.75

client_cache_size

Description

Set the number of inodes that the client keeps in the metadata cache.

Type

Integer

Default

16384 (16 MB)

client_caps_release_delay

Description

Set the delay between capability releases in seconds. The delay sets how many seconds a client waits to release capabilities that it no longer needs in case the capabilities are needed for another user-space operation.

Type

Integer

Default

5 (seconds)

client_debug_force_sync_read

Description

If set to **true**, clients read data directly from OSDs instead of using a local page cache.

Type

Boolean

Default

false

client_dirsize_rbytes

Description

If set to **true**, use the recursive size of a directory (that is, total of all descendants).

Type

Boolean

Default

true

client_max_inline_size

Description

Set the maximum size of inlined data stored in a file inode rather than in a separate data object in RADOS. This setting only applies if the **inline_data** flag is set on the MDS map.

Type

Integer

Default

4096

client_metadata

Description

Comma-delimited strings for client metadata sent to each MDS, in addition to the automatically generated version, host name, and other metadata.

Type

String

Default

"" (no additional metadata)

client_mount_gid

Description

Set the group ID of CephFS mount.

Type

Integer

Default

-1

client_mount_timeout

Description

Set the timeout for CephFS mount in seconds. If the storage cluster is not using CephFS, this value refers to the number of seconds that a Ceph Monitor node attempts to communicate with other Ceph Monitor nodes in the storage cluster. If the Ceph Monitor node cannot reach the

other nodes, it times out after the defined number of seconds. In addition, any active **libvirt/librados** operations time out at the same time. Setting the timeout value allows applications to fail after the specified time interval, instead of blocking other operations.

Type

Float

Default**300.0****client_mount_uid****Description**

Set the user ID of CephFS mount.

Type

Integer

Default**-1****client_mountpoint****Description**

An alternative to the **-r** option of the **ceph-fuse** command. See

Type

String

Default

/

client_oc**Description**

Enable object caching.

Type

Boolean

Default**true****client_oc_max_dirty****Description**

Set the maximum number of dirty bytes in the object cache.

Type

Integer

Default**104857600** (100MB)**client_oc_max_dirty_age****Description**

Set the maximum age in seconds of dirty data in the object cache before writeback.

Type

Float

Default

5.0 (seconds)

client_oc_max_objects

Description

Set the maximum number of objects in the object cache.

Type

Integer

Default

1000

client_oc_size

Description

Set how many bytes of data will the client cache.

Type

Integer

Default

209715200 (200 MB)

client_oc_target_dirty

Description

Set the target size of dirty data. Red Hat recommends to keep this number low.

Type

Integer

Default

8388608 (8MB)

client_permissions

Description

Check client permissions on all I/O operations.

Type

Boolean

Default

true

client_quota_df

Description

Report root directory quota for the **statfs** operation.

Type

Boolean

Default

true

client_readahead_max_bytes**Description**

Set the maximum number of bytes that the kernel reads ahead for future read operations. Overridden by the **client_readahead_max_periods** setting.

Type

Integer

Default

0 (unlimited)

client_readahead_max_periods**Description**

Set the number of file layout periods (object size * number of stripes) that the kernel reads ahead. Overrides the **client_readahead_max_bytes** setting.

Type

Integer

Default

4

client_readahead_min**Description**

Set the minimum number bytes that the kernel reads ahead.

Type

Integer

Default

131072 (128KB)

client_snapdir**Description**

Set the snapshot directory name.

Type

String

Default

".snap"

client_tick_interval**Description**

Set the interval in seconds between capability renewal and other upkeep.

Type

Float

Default

1.0

client_use_random_mds**Description**

Choose random MDS for each request.

Type

Boolean

Default

false

fuse_default_permissions**Description**

When set to **false**, the **ceph-fuse** utility checks does its own permissions checking, instead of relying on the permissions enforcement in FUSE. Set to **false** together with the **client acl type=posix_acl** option to enable POSIX ACL.

Type

Boolean

Default

true

Developer Options**IMPORTANT**

These options are internal. They are listed here only to complete the list of options.

client_debug_getattr_caps**Description**

Check if the reply from the MDS contains required capabilities.

Type

Boolean

Default

false

client_debug_inject_tick_delay**Description**

Add artificial delay between client ticks.

Type

Integer

Default

0

client_inject_fixed_oldest_tid**Description, Type**

Boolean

Default

false

client_inject_release_failure**Description, Type**

Boolean

Default**false****client_trace****Description**

The path to the trace file for all file operations. The output is designed to be used by the Ceph synthetic client. See the **ceph-syn(8)** manual page for details.

Type

String

Default

"" (disabled)